

rdbxx

1.0.5

Generated by Doxygen 1.5.6

Tue Sep 15 11:07:15 2009

Contents

1	RDB User's Guide	1
1.1	Copyright	1
1.2	Introduction	2
1.3	Basic Interface	2
1.4	Specialized Interface	2
1.5	Examples	3
2	Basic Interface	3
2.1	Creating RDB objects for reading or writing	3
2.2	RDB header and table information	4
2.3	Accessing comments and columns	4
2.4	Table I/O	5
2.5	Rewinding tables	6
2.6	Automatic indexing for column data	6
2.7	Group columns	6
2.8	Creating RDB objects	7
2.9	Header and table size	7
2.10	Comment initializers	7
2.10.1	Examples	7
2.11	Comment accessors	8
2.12	Column initializers	8
2.13	Column accessors	9
2.13.1	Examples	10
3	Examples	10
4	Introduction	11
4.1	Purpose	11
4.2	RDB format	11
5	Specialized Interface	12

5.1	Data storage	12
5.1.1	Default data storage	12
5.1.2	Examples	12
5.1.3	User-specified data storage	13
5.1.4	Examples	13
5.1.5	Auto-indexing	13
5.1.6	Examples	14
5.2	Stream manipulation	14
5.2.1	Effects on data storage	14
5.2.2	Limitations	14
6	Directory Hierarchy	14
6.1	Directories	14
7	Class Index	15
7.1	Class Hierarchy	15
8	Class Index	15
8.1	Class List	15
9	Directory Documentation	16
9.1	rdbxx/ Directory Reference	16
10	Class Documentation	16
10.1	RDB Class Reference	16
10.1.1	Detailed Description	26
10.1.2	Member Enumeration Documentation	27
10.1.3	Constructor & Destructor Documentation	27
10.1.4	Member Function Documentation	28
10.1.5	Friends And Related Function Documentation	66
10.1.6	Member Data Documentation	67
10.2	RDBCColumn Class Reference	71
10.2.1	Detailed Description	78

10.2.2	Member Enumeration Documentation	78
10.2.3	Constructor & Destructor Documentation	78
10.2.4	Member Function Documentation	79
10.2.5	Friends And Related Function Documentation	94
10.2.6	Member Data Documentation	96
10.3	RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 > Class Template Reference	98
10.3.1	Detailed Description	101
10.3.2	Constructor & Destructor Documentation	102
10.3.3	Member Function Documentation	103
10.3.4	Member Data Documentation	113
10.4	RDBComment Class Reference	114
10.4.1	Detailed Description	116
10.4.2	Constructor & Destructor Documentation	116
10.4.3	Member Function Documentation	117
10.4.4	Friends And Related Function Documentation	120
10.5	RDBErr Class Reference	121
10.5.1	Detailed Description	121
10.5.2	Constructor & Destructor Documentation	121
10.6	simpleRDBTable< Type > Class Template Reference	122
10.6.1	Detailed Description	123
10.6.2	Member Function Documentation	124

1 RDB User's Guide

1.1 Copyright

Copyright (C) 2006 Smithsonian Astrophysical Observatory

This file is part of rdbxx

rdbxx is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

rdbxx is distributed in the hope that it will be useful, but WITHOUT ANY WAR-

RANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA

1.2 Introduction

- [Purpose](#)
- [RDB format](#)

1.3 Basic Interface

- [Creating RDB objects for reading or writing](#)
- [RDB header and table information](#)
- [Accessing comments and columns](#)
- [Table I/O](#)
- [Rewinding tables](#)
- [Automatic indexing for column data](#)
- [Group columns](#)
- [Creating RDB objects](#)
- [Header and table size](#)
- [Comment initializers](#)
- [Comment accessors](#)
- [Column initializers](#)
- [Column accessors](#)

1.4 Specialized Interface

- [Data storage](#)
 1. [Default data storage](#)
 2. [User-specified data storage](#)

- 3. [Auto-indexing](#)
- [Stream manipulation](#)
 - 1. [Effects on data storage](#)
 - 2. [Limitations](#)

1.5 Examples

- [Creating an output file](#)
- [A simple filter](#)
- [Using group columns](#)

Author:

[M. Tibbetts](#)

2 Basic Interface

2.1 Creating RDB objects for reading or writing

The [RDB](#) library allows the user to read or write [RDB](#) formatted data. Users may attach an [RDB](#) object to either a file or a C++ stream. The object may be associated with a file or stream either at the time it is created, via the constructors [RDB::RDB](#), or after the object is created, via the [RDB::open](#) methods.

```
// Open for input, using explicit open mode.
RDB irdb( "input.rdb", ios::in );

// Open for input, using default open mode.
RDB irdb( "input.rdb" );

// Open for input, using a pointer to an istream.
RDB irdb( &cin );

// Open for output. The explicit open mode is required, otherwise
// it will default to open for input.
RDB ordb( "output.rdb", ios::out );

// Create the object with no file or stream specified.
RDB ordb;
// Specify the stream via the RDB::open(ostream) method.
ordb.open( &cout );
// Or, specify the file via the RDB::open(string,ios::openmode) method.
ordb.open( "output.rdb", ios::out );
```

2.2 RDB header and table information

Information about the number of comments, columns, and rows are available using the `RDB::nComments`, `RDB::nColumns()`, and `RDB::nRows` methods. It is important to note that the first two are trivial queries, but determining the number of rows involves reading the entire table.

```
irdb.open( &cin );

for ( size_t idx = 0; idx < irdb.nColumns(); idx++ ) {
    cout << idx << ": " << irdb.getColumn( idx )->getName( ) << endl;
}

// This could take awhile...
cout << "There are " << irdb.nRows( ) << " rows" << endl;
```

2.3 Accessing comments and columns

An `RDB` object allows the user to add comments and columns as well as access existing comments and columns. When an `RDB` object is opened for reading, the `RDB` header is parsed for comments and columns. Any comment or column found is placed in the `RDB` object. When an `RDB` object is opened for writing, no comments or columns are present in the object.

To access an existing comment or column the user may reference the comment or column by index. Comments/Columns are indexed beginning at 0. If the user is requesting an index beyond the range of comments/columns contained in the `RDB` object, an `RDBErrNotFound` object is thrown or `RDB::_errno` is set. If the user is adding a comment/column and specifies an index beyond the range contained in the `RDB` object, the comment/column is added to the end of the list.

It is important to note that comments are returned as references to the underlying object while columns are returned as pointers to the underlying object. This is to allow columns of different datatypes to be stored in the same `RDB` object container.

```
// Foreach column...
for ( size_t idx = 0; idx < irdb.nColumns(); idx++ ) {
    // Print the name and definition.
    cout << irdb.getColumn( idx )->getName( ) << " | "
        << irdb.getColumn( idx )->getDef( ) << endl;

    // Note the use of the '->', pointer dereference, operator.
}

// Set the error handling behavior to throw exceptions.
irdb.setThrow( true );
try {
    // Ask for on comment beyond what we have.
```

```

irdb.getComment( irdb.nComments( ) );

// NOTE: the use of the '.', dot, operator.

} catch ( RDBErr& rdberr ) {
    // Catch the exception that will be thrown.
    cerr << "This will fail because comment indices start at 0." << endl;
}

// Here we check how many comments there are and then add one to
// the end.
size_t ncomments_before = irdb.nComments( );
irdb.setComment( "Add one comment to the end..." );
if ( ncomments_before != irdb.nComments( ) ) {
    cout << "Now there's one more comment..." << endl;
}

```

It is also possible to access an existing comment/column or add a new comment/column by specifying the comment keyword/column name. Once, again if the comment/column is being added and no matching keyword/name is found, a new comment/column is added to the end of the list. If the comment/column is being returned and not matching keyword/name is found, an `RDBErrNotFound` object is thrown or `RDB::errno` is set.

```
RDBColumn* col = irdb.getColumn( "x_err" );
```

Comments and columns are stored in [RDBComment](#) and [RDBColumn](#) objects respectively. The [RDB](#) object provides access to the [RDBComment](#) and [RDBColumn](#) objects it contains. For access to the constituent parts of either a comment or a column, the user may use the respective class interfaces.

```

// To access a column name, first get the column then ask it for
// its name...
irdb.getColumn( 3 )->getName( );

// To reset a comment header variable, first get the comment then
// set its value...
irdb.getComment( "foo" ).setValue( "Not bar" );

```

2.4 Table I/O

Table input and output are handled by the [RDB::read](#) and [RDB::write](#) methods. For input, [RDB::read](#) reads one row from the table, parsing it into the [RDB](#) object's columns. It checks to ensure the proper number of columns are found on each row,

2.5 Rewinding tables

With [RDB](#) objects, the user has the possibility of rewinding the [RDB](#) table. The object remembers the location of the first element of the first row or data. At any point, the object may be rewound, with the [RDB::rewind](#) method, to that point. [RDBColumn::rewind](#) is called on all columns associated with the [RDB](#) object.

It is important to note that if the [RDB](#) object was opened with a stream, rather than a filename, the stream must have the ability to seek. Rewinding an [RDB](#) object opened with `cin` or `cout` will fail.

2.6 Automatic indexing for column data

2.7 Group columns

[RDB](#) objects use the [RDB::newGroup](#) method to monitor [RDBColumns](#) which have grouping activated. [RDB::newGroup](#) scans the [RDBColumns](#) associated with the object and calls [RDBColumn::newGroup](#) on each column. If any column returns true, [RDB::newGroup](#) returns true.

```
double sum;
int cnt;
string group;

irdb.getColumn( "break" )->setGroup( true );

while ( irdb.read( ) ) {
    if ( irdb.newGroup( ) ) {
        if ( irdb.getColumn( "_NR" )->getDataLong( ) ) {
            // Write out old group's stats...
            cout << "Avg for group " << group << " == " << sum / cnt << endl;
        }

        // Reset accumulators...
        sum = 0.0;
        cnt = 0;
        group = irdb.getColumn( "break" )->getString( );
    }

    // Accumulate statistics on other columns...
    sum += irdb.getColumn( "data" )->getDataDouble( );
    cnt++;
}
```

2.8 Creating RDB objects

RDB objects are created using any of the class constructors, `RDB::RDB(const string&, const ios::open_mode)`, `RDB::RDB(istream)` or `RDB::RDB(const RDB&)`. The filename constructor doubles as the default constructor for the class. If no filename is specified, an object is created but no stream is attached to it. The `RDB::open()` method must be called to attach the object to a stream.

If the filename constructor is used with a filename specified, then the default is to open the file for reading. The user may explicitly set the open mode for output though.

The copy constructor does a shallow copy of the object provided as an argument. The new object is linked to the argument. Modification to the first objects RDBColumns will show up in the second objects RDBColumns.

2.9 Header and table size

Information about the number of comments, columns, rows are available using the `RDB::nComments()`, `RDB::nColumns()`, or `RDB::nRows()` methods.

2.10 Comment initializers

Various initialization functions are provided to set or add comments to an RDB. They methods allow the user to set or add entire `RDBComment` objects, or parts of RDB-Comments such as the keyword or value.

- `RDB::setComment()`
- `RDB::setCommentText()`
- `RDB::setCommentKeyword()`
- `RDB::setCommentValue()`

Each method allows the user to either specify the comment index, thereby replacing the existing `RDBComment`, or to leave out the index, thereby appending a new `RDBComment` to the end of the header.

2.10.1 Examples

Here an entire `RDBComment` object is added to the header.

```
RDBComment comment( "#: comment_variable = comment value" );  
rdb.setComment( comment );
```

Here we overwrite the second comment with a new one.

```
rdb.setComment( comment, 2 );
```

2.11 Comment accessors

Comment accessors allow the user to retrieve all or part of the [RDBComment](#). Once again there is a separate method for each part of the [RDBComment](#).

- [RDB::getComment\(\)](#)
- [RDB::getCommentText\(\)](#)
- [RDB::getCommentKeyword\(\)](#)
- [RDB::getCommentValue\(\)](#)

Each method has two signatures. The first signature allows the user to specify which comment to act upon by its index in the header. The second signature allows the user to specify which comment to act upon via keyword. It should be noted that if the comment does not explicitly contain a keyword = value construct no keyword is stored for the comment.

Each signature throws an exception if a comment matching either the index or keyword is not found. For functions specifying the index, an [IndexOutOfRangeException](#) is thrown. For the functions specifying the keyword, a [KeyNotFoundException](#) is thrown.

2.12 Column initializers

Various initialization functions are provided to set or add columns to an [RDB](#). They methods allow the user to set or add entire [RDBColumn](#) objects, or parts of RDB-Columns such as the name, definition, or value.

- [RDB::setColumn\(\)](#)
- [RDB::setColumnNameDef\(\)](#)
- [RDB::setColumnName\(\)](#)
- [RDB::setColumnDef\(\)](#)
- [RDB::setColumnWidth\(\)](#)
- [RDB::setColumnType\(\)](#)
- [RDB::setColumnJust\(\)](#)

- `RDB::setColumnDesc()`
- `RDB::setColumnValue()`

Each method allows the user to either specify either the column index or the column name. The user may provide an entire `RDBCColumn` object, as is the case with the `RDB::setColumn()` methods. If the index is out of range or the name is not the name of an existing column, the `RDBCColumn` object is added to the `RDB`. Otherwise, the `RDBCColumn` object replaces the existing object.

Each in turn throws an exception if the column is not found. In the case of columns specified by index, an `IndexOutOfRangeException` is thrown. In the case of columns specified by name, a `KeyNotFoundException` is thrown. The methods which provide a column definition can also throw `BadHeaderException` if the definition is not of the proper form.

2.13 Column accessors

Column accessors allow the user to retrieve all or part of the `RDBCColumn`. Once again there is a separate method for each part of the `RDBCColumn`.

- `RDB::getColumn()`
- `RDB::getColumnNameDef()`
- `RDB::getColumnName()`
- `RDB::getColumnDef()`
- `RDB::getColumnWidth()`
- `RDB::getColumnType()`
- `RDB::getColumnJust()`
- `RDB::getColumnDesc()`
- `RDB::getColumnValue()`

Each method allows the user to either specify either the column index or the column name.

Each in turn throws an exception if the column is not found. In the case of columns specified by index, an `IndexOutOfRangeException` is thrown. In the case of columns specified by name, a `KeyNotFoundException` is thrown.

2.13.1 Examples

Here's a neat trick. You can link input and output tables by sharing `RDBColumns`. In this example the input is passed to the output. However, after linking the two [RDB](#) objects, the user doesn't have to explicitly set the values on the output table. The output will just use the values from the latest read from the input.

```
RDB irdb(&cin);
RDB ordb(&cout);

// This part takes a pointer to the column from input and gives it
// to the output. Now they point at the same RDBColumn...
for ( int i = 0; i < input.nColumns(); i++ )
    ordb.setColumn( irdb.getColumn( i ) );

ordb.writeHeader( );

// Because the two tables share pointers to the same RDBColumns, a
// call to read sets the values of the data in the output as well
// as the input. So now, a call to write will write the values
// from the read.
while ( irdb.read( ) )
    ordb.write( );
```

3 Examples

example1.cc

example2.cc

example3.cc

The following example demonstrates the use of the class [simpleRDBTable](#). Given the following rdb file: `hrc-size.cc`

The rows of the rdb file can be initialized in the class `ChipSize`: `ChipSize.h`

ChipSize.cc ChipSize.cc

An example to invoke the [simpleRDBTable](#) class. testsimple.cc

4 Introduction

4.1 Purpose

The [RDB](#) library was created to handle input and output related tasks for [RDB](#) tables. The interface consists of multiple layers. The casual user may use the library through the [RDB](#) object interface exclusively. This interface allows the user to open, close, read from, and write to [RDB](#) tables. The interface handles provides default means of interpreting data types of the columns as well as default data storage management. Examples of basic table manipulations via the [RDB](#) object interface are available.

For some tasks the user may wish to modify the structure of a table or explicitly manage the location and memory allocation of the data. In these cases, the user will need to make use of the [RDBColumn](#) interface in addition to the [RDB](#) interface. Examples of more advance table manipulations using the [RDBColumn](#) interface are also available.

4.2 RDB format

[RDB](#) is an ASCII text format. An [RDB](#) table consists of three distinct elements:

- Comments (Comments are optional)
- Header (The header is mandatory)
- Data (The data are optional, though it would be a trivial table with no data...)

A comment is any line beginning zero or more spaces followed by a sharp sign (#). Characters following the sharp sign are considered to be the body of the comment. Comments may have additional structure within the body. It is possible to have comment variables, also known as header variables. A comment variable is said to exist if the sharp sign is immediately followed by a colon (:). The first word, non-whitespace and non-equal sign (=) characters, following the colon is the comment variable. The value of the comment variable is seperated from the variable by optional space (' ') and tab ('\t') characters and a mandatory equal sign. The variable value is then any text between the equal sign and the newline. It is common to restrict comments to the initial section of the file

The header consists of two lines. The first contains a tab separated list of column names. Each column name is separated by a single tab. The second line contains tab separated column definitions. Definitions consist of an optional numeric value indicating the width, an S(string), N(umeric), or M(onth) character denoting the type of the data, an optional < or > character indicating left or right justification of data, and an optional text description.

The data consist of tab separated values, one per column name.

For a more definitive description of the format see <http://hea-www.harvard.edu/MST/simul/software/docs/html/perlrbdb/rdb.html>.

5 Specialized Interface

5.1 Data storage

The default behavior of [RDB](#) object is to allocate space for data storage without pestering the user. When the object is used to read an [RDB](#) table, it parses the file and creates [RDBComments](#) for each comment line and [RDBColumn](#) of the appropriate datatype for each column.

5.1.1 Default data storage

When left to its own devices, an [RDB](#) object will manage memory usage on its own with no need for intervention from the user. This management essentially consists of allocating [RDBComment](#) objects and [RDBColumn](#) objects on demand and deleting them via the destructor.

Likewise, the underlying [RDBColumn](#) objects used by the [RDB](#) object handle their own memory needs by default. So, upon creation an [RDBColumn](#) object allocates a single element for data storage. [RDBColumns](#) handle the deletion of this data storage element in the call to their destructor.

Copies of the values can be accessed via the [RDB::getValue\(\)](#) methods or the [RDBColumn::getData\(\)](#) methods.

5.1.2 Examples

Using the default data storage and the [RDB::getValue\(\)](#) method.

```
while ( rdbtable.read( ) )  
    cout << "Column 0 value == " << rdbtable.getValue( 0 ) << endl;
```

5.1.3 User-specified data storage

Sometimes the user may want to handle memory for data storage on their own. It is possible to supply the [RDB](#) object or [RDBColumn](#) a pointer to memory the user has allocated via the [RDBColumn::mapData\(\)](#) methods. By doing so the user can avoid calls to [RDBColumn::getData\(\)](#) or [RDB::getValue\(\)](#) and simply access the value via the pointer to the storage they provided.

Any memory the user provides via [RDBColumn::mapData\(\)](#) must be managed, i.e. deleted, by the user.

By providing their own memory for data storage, the user can also make use of [RDB](#) object's ability to auto-index arrays used for storage.

5.1.4 Examples

With user supplied data storage there's no need to use the [RDB::getValue\(\)](#) method.

```
double d;
rdhtable.getColumn( 0 )->mapData( d );

while ( rdhtable.read( ) )
    cout << "Column 0 value == " << d << endl;
```

You can also store data from multiple rows.

```
double d_arr[10];
rdhtable.getColumn( 0 )->mapData( d, 10 );

int i = 0;
while ( rdhtable.read( ) ) {
    cout << "Column 0 current value == " << d[i%10] << endl;
    cout << "Column 0 previous value == " << d[(i-1)%10] << endl;
    i++;
}
```

5.1.5 Auto-indexing

When the user supplies arrays of data storage via [RDBColumn::mapData\(\)](#) [RDB](#) objects and [RDBColumn](#) will auto-index the arrays. As data is read or written, the default behavior is to increment the index into the user supplied array for data storage. It is possible then to store multiple rows of data.

[RDB](#) objects and [RDBColumn](#) increment the array index until the last element of the array provided by the user is reached. It then loops to the first element and begins over writing data.

It is possible to stop the auto-incrementing by calling the [RDB::autoIdx\(\)](#) method. This temporarily turns off the auto-incrementing behavior until the next read or write.

5.1.6 Examples

In this example we want to store only the lines with negative data. So we use user supplied data storage and the `RDB::autoIdx()` method.

```
double* d = new double( rdbtable.nRows( ) );
rdbtable.getColumn( 0 )->mapData( d, rdbtable.nRows( ) );

int i = 0;
while ( rdbtable.read( ) ) {
    if ( 0 <= d[i] ) {
        rdbtable.noAdvance( );
    }
    else
        i++;
}
```

5.2 Stream manipulation

5.2.1 Effects on data storage

If the `RDB` object is attached to a file stream, it is possible to rewind the file to the first line of data. `RDB::rewind()` will move the file pointer back to the first data element. It also resets the array index for user supplied data storage. So, after a call to `RDB::rewind()`, all user supplied data storage will be pointing to the first element in the array.

5.2.2 Limitations

As noted above, `RDB::rewind` only works when the `RDB` object is attached to a stream that allows rewinding. `RDB::rewind()` will fail if the `RDB` is attached to `STDIN` or `STDOUT`.

6 Directory Hierarchy

6.1 Directories

This directory hierarchy is sorted roughly, but not completely, alphabetically:

rdboxx

16

7 Class Index

7.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

RDB	16
simpleRDBTable< Type >	122
RDBColumn	71
RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >	98
RDBComment	114
RDBErr	121

8 Class Index

8.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

RDB (Provides interface for manipulating RDB tables)	16
RDBColumn (Provides interface for general column related methods)	71
RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 > (Parameterizes RDBColumn interface for many data types)	98
RDBComment (Provides interface for manipulating RDB comments)	114
RDBErr (The parent class for all RDB related exceptions)	121
simpleRDBTable< Type >	122

9 Directory Documentation

9.1 rdbxx/ Directory Reference

rdbxx

Files

- file **RDB.cc**
- file **RDB.h**
- file **RDBColumn.cc**
- file **RDBColumn.h**
- file **RDBColumnTmpl.cc**
- file **RDBColumnTmpl.h**
- file **RDBComment.cc**
- file **RDBComment.h**
- file **RDBErr.cc**
- file **RDBErr.h**
- file **simpleRDBTable.cc**
- file **simpleRDBTable.h**


10 Class Documentation

10.1 RDB Class Reference


Provides interface for manipulating [RDB](#) tables.

```
#include <RDB.h>
```

Inheritance diagram for RDB:



Collaboration diagram for RDB:



Public Types

Enumerations for read/write/group return status.

- enum **Status** { **REOF** = 0x00, **REOL** = 0x01, **REOG** = 0x02, **RBOG** = 0x04 }

Acceptable column justifications.

Public Member Functions

Constructing and destructing and initializing RDB objects.

- RDB** (const string &name="", ios::openmode mode=ios::in) throw (RDBErr)
*Attaches **RDB** object to a file.*
- RDB** (istream *isptr) throw (RDBErr)
*Attaches **RDB** object to an istream.*
- RDB** (ostream *osptr) throw (RDBErr)
*Attaches **RDB** object to an ostream.*
- RDB** (const **RDB** &rdb) throw (RDBErr)
*Copies **RDB** object.*
- ~RDB** (void)
*Deletes resources allocated by the **RDB** object.*

I/O related operations.

- void **open** (const string &name, ios::openmode mode=ios::in) throw (RDBErr)

Attaches *RDB* object to a file.

- void **open** (istream *isptr) throw (RDBErr)
*Attaches *RDB* object to an istream.*
- void **open** (ostream *osptr) throw (RDBErr)
*Attaches *RDB* object to an ostream.*
- void **open** (const *RDB* &rdb) throw (RDBErr)
*Copies *RDB* object.*
- void **close** (void)
*Closes the stream attached to *RDB* object.*
- int **read** (void) throw (RDBErr)
Read a line of data from the istream.
- bool **write** (void) throw (RDBErr)
Write a line of data to the ostream.
- bool **rewind** (void) throw (RDBErr)
Rewind the stream to the beginning of the first row of data.

Auto-indexing related methods.

- bool **autoIdx** (void) const
Indicates if auto-indexing is activated.
- void **autoIdx** (const bool on)
Activates/deactivates auto-indexing.
- void **advanceIdx** (void)
*Increments the indices in the *RDBColumn* data elements.*

Column group manipulation (break columns)

- void **setGroup** (const string &name, bool group=true) throw (RDBErr)
Turn on/off group status for the named column.
- void **setGroup** (const int idx, bool group=true) throw (RDBErr)
Turn on/off group status for the indexed column.
- bool **getGroup** (const string &name) throw (RDBErr)
Returns group status, true if its a new group, for the named column.

- bool [getGroup](#) (const int idx) throw (RDBErr)
Returns group status, true if its a new group, for the indexed column.
- bool [newGroup](#) (void)
Checks if any column indicates a new group.

Comment accessors.

- void [setComment](#) (const string &comm, const int idx=-1)
Add [RDBComment](#) in header of [RDB](#) object.
- void [setComment](#) ([RDBComment](#) &comm, const int idx=-1)
Add or replace [RDBComment](#) in header of [RDB](#) object.
- void [setComment](#) ([RDBComment](#) &comm, const string &name, const size_t idx=0)
Add or replace [RDBComment](#) in header of [RDB](#) object.
- void [setComment](#) (const [RDB](#) &rdb)
Copy all comments from an existing [RDB](#) object.
- [RDBComment](#) & [getComment](#) (const size_t idx) throw (RDBErr)
Return [RDBComment](#) at given index.
- [RDBComment](#) & [getComment](#) (const string &name, const size_t idx=0) throw (RDBErr)
Return [RDBComment](#) with given keyword.

Column accessors.

- void [setColumn](#) (const string &name, const string &def, const int idx=-1)
Add an [RDBColumn](#) in [RDB](#) object.
- void [setColumn](#) ([RDBColumn](#) *col, const int idx=-1)
Add or replace [RDBColumn](#) in [RDB](#) object.
- void [setColumn](#) ([RDBColumn](#) *col, const string &name, const size_t idx=0)
Add of replace [RDBColumn](#) in [RDB](#) object.
- void [setColumn](#) (const [RDB](#) &rdb)
Copy all columns from an existing [RDB](#) object.
- [RDBColumn](#) * [getColumn](#) (const size_t idx) throw (RDBErr)
Return pointer to [RDBColumn](#) at given index.

- `RDBColumn * getColumn` (const string &name, const size_t idx=0) throw (RDBErr)
Return pointer to [RDBColumn](#) with given name.

Column index based accessors.

- void `setName` (const size_t idx, const string &name) throw (RDBErr)
Modify the name of the [RDBColumn](#) at idx.
- void `setDef` (const size_t idx, const string &def) throw (RDBErr)
Modify the definition of the [RDBColumn](#) at idx.
- void `setWidth` (const size_t idx, const long width) throw (RDBErr)
Modify the width of the [RDBColumn](#) at idx.
- void `setType` (const size_t idx, const [RDBColumn::Type](#) type) throw (RDBErr)
Modify the type of the [RDBColumn](#) at idx.
- void `setJust` (const size_t idx, const [RDBColumn::Just](#) just) throw (RDBErr)
Modify the justification of the [RDBColumn](#) at idx.
- void `setDesc` (const size_t idx, const string &desc) throw (RDBErr)
Modify the description of the [RDBColumn](#) at idx.
- void `mapData` (const size_t idx, double data[], const size_t nelems=1) throw (RDBErr)
Map [RDBColumn](#) data to user-supplied memory.
- void `mapData` (const size_t idx, long data[], const size_t nelems=1) throw (RDBErr)
Map [RDBColumn](#) data to user-supplied memory.
- void `mapData` (const size_t idx, string data[], const size_t nelems=1) throw (RDBErr)
Map [RDBColumn](#) data to user-supplied memory.
- void `setData` (const size_t idx, const double data) throw (RDBErr)
Sets the data value of [RDBColumn](#), converting as necessary.
- void `setData` (const size_t idx, const long data) throw (RDBErr)
Sets the data value of [RDBColumn](#), converting as necessary.
- void `setData` (const size_t idx, const string &data) throw (RDBErr)
Sets the data value of [RDBColumn](#), converting as necessary.

- void `getName` (const size_t idx, string &name) const throw (RDBErr)
Return the name of the [RDBColumn](#) at idx.
- void `getDef` (const size_t idx, string &def) throw (RDBErr)
Return the definition of the [RDBColumn](#) at idx.
- void `getWidth` (const size_t idx, long &width) const throw (RDBErr)
Return the width of the [RDBColumn](#) at idx.
- void `getType` (const size_t idx, [RDBColumn::Type](#) &type) const throw (RDBErr)
Return the type of the [RDBColumn](#) at idx.
- void `getJust` (const size_t idx, [RDBColumn::Just](#) &just) const throw (RDBErr)
Return the just of the [RDBColumn](#) at idx.
- void `getDesc` (const size_t idx, string &desc) const throw (RDBErr)
Return the description of the [RDBColumn](#) at idx.
- void `getData` (const size_t idx, double &data) throw (RDBErr)
Return the data of the [RDBColumn](#) at idx, converting if necessary.
- void `getData` (const size_t idx, long &data) throw (RDBErr)
Return the data of the [RDBColumn](#) at idx, converting if necessary.
- void `getData` (const size_t idx, string &data) throw (RDBErr)
Return the data of the [RDBColumn](#) at idx, converting if necessary.
- string `getName` (const size_t idx) const throw (RDBErr)
Return the name of the [RDBColumn](#) at idx.
- string `getDef` (const size_t idx) throw (RDBErr)
Return the definition of the [RDBColumn](#) at idx.
- long `getWidth` (const size_t idx) const throw (RDBErr)
Return the width of the [RDBColumn](#) at idx.
- [RDBColumn::Type](#) `getType` (const size_t idx) const throw (RDBErr)
Return the type of the [RDBColumn](#) at idx.
- [RDBColumn::Just](#) `getJust` (const size_t idx) const throw (RDBErr)
Return the justification of the [RDBColumn](#) at idx.
- string `getDesc` (const size_t idx) const throw (RDBErr)
Return the description of the [RDBColumn](#) at idx.

- double [getDataDouble](#) (const size_t idx) throw (RDBErr)
Return the data of the [RDBColumn](#) at idx, converting if necessary.
- long [getDataLong](#) (const size_t idx) throw (RDBErr)
Return the data of the [RDBColumn](#) at idx, converting if necessary.
- string [getDataString](#) (const size_t idx) throw (RDBErr)
Return the data of the [RDBColumn](#) at idx, converting if necessary.

Column name based accessors.

- void [setName](#) (const string &name, const string &newname) throw (RDBErr)
Modify the [RDBColumn](#) name.
- void [setDef](#) (const string &name, const string &def) throw (RDBErr)
Modify the [RDBColumn](#) definition.
- void [setWidth](#) (const string &name, const long width) throw (RDBErr)
Modify the [RDBColumn](#) width.
- void [setType](#) (const string &name, const [RDBColumn::Type](#) type) throw (RDBErr)
Modify the [RDBColumn](#) type.
- void [setJust](#) (const string &name, const [RDBColumn::Just](#) just) throw (RDBErr)
Modify the [RDBColumn](#) justification.
- void [setDesc](#) (const string &name, const string &desc) throw (RDBErr)
Modify the [RDBColumn](#) description.
- void [mapData](#) (const string &name, double data[], const size_t nelems=1) throw (RDBErr)
Map [RDBColumn](#) data to user-supplied memory.
- void [mapData](#) (const string &name, long data[], const size_t nelems=1) throw (RDBErr)
Map [RDBColumn](#) data to user-supplied memory.
- void [mapData](#) (const string &name, string data[], const size_t nelems=1) throw (RDBErr)
Map [RDBColumn](#) data to user-supplied memory.
- void [setData](#) (const string &name, const double data) throw (RDBErr)

Modify the *RDBColumn* data, converting if necessary.

- void **setData** (const string &name, const long data) throw (RDBErr)
Modify the *RDBColumn* data, converting if necessary.
- void **setData** (const string &name, const string &data) throw (RDBErr)
Modify the *RDBColumn* data, converting if necessary.
- void **getName** (const string &name, string &namefound) const throw (RDBErr)
Return the name of the *RDBColumn*.
- void **getDef** (const string &name, string &def) throw (RDBErr)
Return the definition of the *RDBColumn*.
- void **getWidth** (const string &name, long &width) const throw (RDBErr)
Return the width of the *RDBColumn*.
- void **getType** (const string &name, *RDBColumn::Type* &type) const throw (RDBErr)
Return the type of the *RDBColumn*.
- void **getJust** (const string &name, *RDBColumn::Just* &just) const throw (RDBErr)
Return the justification of the *RDBColumn*.
- void **getDesc** (const string &name, string &desc) const throw (RDBErr)
Return the description of the *RDBColumn*.
- void **getData** (const string &name, double &data) throw (RDBErr)
Return the data of the *RDBColumn*, converting if necessary.
- void **getData** (const string &name, long &data) throw (RDBErr)
Return the data of the *RDBColumn*, converting if necessary.
- void **getData** (const string &name, string &data) throw (RDBErr)
Return the data of the *RDBColumn*, converting if necessary.
- string **getName** (const string &name) const throw (RDBErr)
Return the name of the *RDBColumn*.
- string **getDef** (const string &name) throw (RDBErr)
Return the definition of the *RDBColumn*.
- long **getWidth** (const string &name) const throw (RDBErr)
Return the width of the *RDBColumn*.

- [RDBColumn::Type getType](#) (const string &name) const throw (RDBErr)
Return the type of the [RDBColumn](#).
- [RDBColumn::Just getJust](#) (const string &name) const throw (RDBErr)
Return the justification of the [RDBColumn](#).
- string [getDesc](#) (const string &name) const throw (RDBErr)
Return the description of the [RDBColumn](#).
- double [getDataDouble](#) (const string &name) throw (RDBErr)
Return the data of the [RDBColumn](#), converting if necessary.
- long [getDataLong](#) (const string &name) throw (RDBErr)
Return the data of the [RDBColumn](#), converting if necessary.
- string [getDataString](#) (const string &name) throw (RDBErr)
Return the data of the [RDBColumn](#), converting if necessary.

Table and header statistics.

- size_t [nComments](#) (void) const
Return number of comments in [RDB](#) object.
- size_t [nColumns](#) (void) const
Return number of columns in [RDB](#) object.
- size_t [nRows](#) (void)
Return number of rows in [RDB](#) object.

Protected Member Functions

- void [parseHeader](#) (void) throw (RDBErr)
Parse header, i.e. comments and column names and definitions.
- vector< string > [parseLine](#) (const string &line) const
Parse fields in a row.
- size_t [parseLine](#) (bool &newgroup) throw (RDBErr)
Parse fields in a row.

Protected Attributes

- string [_filename](#)
Name of [RDB](#) file.
- ios::openmode [_mode](#)
Open mode of the associated stream.
- istream * [_isptr](#)
Istream attached to data file.
- ostream * [_osptr](#)
Ostream attached to data file.
- bool [_myisptr](#)
Indicates if [RDB](#) object is responsible for deallocating the istream.
- bool [_myosptr](#)
Indicates if [RDB](#) object is responsible for deallocating the ostream.
- size_t [_rewindto](#)
Position of beginning of first row of data.
- size_t [_ncomms](#)
Number of comments.
- size_t [_ncols](#)
Number of columns.
- size_t [_nrows](#)
Number of rows.
- bool [_knowrows](#)
Indicates if associated file must be scanned to determine number of rows.
- long [_rownum](#)
*Current **table** row number.*
- long [_frownum](#)
*Current **file** row number.*
- bool [_autoidx](#)
Indicates if [RDBColumn](#) data elements should be advanced.

- bool [_firstread](#)
Indicates if this is the first call to [RDB::read](#).
- bool [_lastread](#)
Indicates if this is the last call to [RDB::read](#).
- bool [_writehdr](#)
Indicates if the header has been output.
- [RDBComment](#) * [_comms](#)
Array of [RDBComments](#).
- [RDBColumn](#) ** [_cols](#)
Array of [RDBColumns](#).
- [RDBLongColumn](#) [_nrcol](#)
Hidden column, containing row number.
- bool * [_mycols](#)
Indicates if [RDB](#) object is responsible for deallocating given [RDBColumn](#).
- string [_line](#)
Line from [RDB](#) table.

Friends

Stream insertion and extraction operators.

- istream & [operator>>](#) (istream &is, [RDB](#) &rdb) throw ([RDBErr](#))
Read table from input stream.
- ostream & [operator<<](#) (ostream &os, [RDB](#) &rdb) throw ([RDBErr](#))
Write table to output stream.

10.1.1 Detailed Description

Provides interface for manipulating [RDB](#) tables.

Definition at line 43 of file [RDB.h](#).

10.1.2 Member Enumeration Documentation

10.1.2.1 enum RDB::Status

Acceptable column justifications.

Definition at line 56 of file RDB.h.

10.1.3 Constructor & Destructor Documentation

10.1.3.1 RDB::RDB (const string & *name* = "", ios::openmode *mode* = ios::in) throw (RDBErr)

Attaches [RDB](#) object to a file.

Parameters:

name the name of the [RDB](#) file.

mode the ios::openmode of the file.

Exceptions:

[RDBErr](#) error opening [RDB](#) file.

[RDBErr](#) error parsing [RDB](#) comment or column name and definition.

[RDBErr](#) error parsing [RDB](#) column definition.

Attaches [RDB](#) object's I/O stream to the file. If mode is set to ios::in, it calls [RDB::parseHeader\(void\)](#) to read comments, column names, and column definitions.

If no filename is specified, then the [RDB::open\(\)](#) method may be used later to attach a file to the object.

Definition at line 118 of file RDB.cc.

10.1.3.2 RDB::RDB (istream * *isptr*) throw (RDBErr)

Attaches [RDB](#) object to an istream.

Parameters:

isptr input stream to attach to the [RDB](#) object.

Exceptions:

[RDBErr](#) error parsing [RDB](#) comment or column name and definition.

[RDBErr](#) error parsing [RDB](#) column definition.

Attaches the istream to the [RDB](#) object. [RDB::parseHeader\(void\)](#) is called to read comments, column names, and column definitions.

Definition at line 164 of file RDB.cc.

10.1.3.3 RDB::RDB (ostream * *osptr*) throw (RDBErr)

Attaches [RDB](#) object to an ostream.

Parameters:

osptr output stream to attach to the [RDB](#) object.

Attaches the ostream to the [RDB](#) object.

Definition at line 199 of file RDB.cc.

10.1.3.4 RDB::RDB (const RDB & *rdb*) throw (RDBErr)

Copies [RDB](#) object.

Parameters:

rdb copy [RDB](#) object.

Makes a copy of the argument.

Definition at line 234 of file RDB.cc.

10.1.3.5 RDB::~~RDB (void)

Deletes resources allocated by the [RDB](#) object.

Deletes RDBComments and RDBColumns. Closes only the streams the object opened. User is responsible for closing streams they supply to the object.

Warning:

If the user supplies an [RDBColumn](#) object via the [RDB::setColumn\(\)](#) method, the user is responsible for deleting that object.

Definition at line 271 of file RDB.cc.

References `_cols`, `_comms`, `_isptr`, `_mycols`, `_ncols`, `_osptr`, and `close()`.

10.1.4 Member Function Documentation

10.1.4.1 void RDB::open (const string & *name*, ios::openmode *mode* = ios::in) throw (RDBErr)

Attaches [RDB](#) object to a file.

Parameters:

name the name of the [RDB](#) file.
mode the ios::openmode of the file.

Exceptions:

[RDBErr](#) error opening [RDB](#) file.
[RDBErr](#) error parsing [RDB](#) comment or column name and definition.
[RDBErr](#) error parsing [RDB](#) column definition.

Attaches [RDB](#) object's I/O stream to the file. If mode is set to ios::in, it calls [RDB::parseHeader\(void\)](#) to read comments, column names, and column definitions.

Warning:

This method closes any previously opened streams.

Definition at line 316 of file RDB.cc.

References `_filename`, `_isptr`, `_mode`, `_myisptr`, `_myosptr`, `_osptr`, `close()`, and `parseHeader()`.

10.1.4.2 void RDB::open (istream * *isptr*) throw (RDBErr)

Attaches [RDB](#) object to an istream.

Parameters:

isptr input stream to attach to the [RDB](#) object.

Exceptions:

[RDBErr](#) error parsing [RDB](#) comments or column names and definitions
[RDBErr](#) error parsing [RDB](#) column definition.

Attaches the istream to the [RDB](#) object. [RDB::parseHeader\(void\)](#) is called to read comments, column names, and column definitions.

Warning:

This method closes any previously opened streams.

Definition at line 400 of file RDB.cc.

References `_filename`, `_isptr`, `_mode`, `close()`, and `parseHeader()`.

10.1.4.3 void RDB::open (ostream * *osptr*) throw (RDBErr)

Attaches [RDB](#) object to an ostream.

Parameters:

osptr output stream to attach to the [RDB](#) object.

Attaches the ostream to the [RDB](#) object.

Warning:

This method closes any previously opened streams.

Definition at line 432 of file RDB.cc.

References `_filename`, `_mode`, `_osptr`, and `close()`.

10.1.4.4 void RDB::open (const RDB & *rdb*) throw (RDBErr)

Copies [RDB](#) object.

Parameters:

rdb copy [RDB](#) object.

Warning:

This method is currently not implemented.

Definition at line 451 of file RDB.cc.

References `_filename`, `_isptr`, `_mode`, `_myisptr`, `_myosptr`, `_osptr`, `close()`, and `parse-Header()`.

10.1.4.5 void RDB::close (void)

Closes the stream attached to [RDB](#) object.

Closes any streams that the [RDB](#) object created.

Definition at line 526 of file RDB.cc.

References `_autoidx`, `_cols`, `_comms`, `_filename`, `_isptr`, `_knowrows`, `_myisptr`, `_myosptr`, `_ncols`, `_ncomms`, `_nrows`, `_osptr`, `_rewindto`, `_rownum`, `_writehdr`, `RDB-Column::getDef()`, `getDef()`, `RDBColumn::getName()`, and `getName()`.

Referenced by `open()`, and `~RDB()`.

10.1.4.6 int RDB::read (void) throw (RDBErr)

Read a line of data from the istream.

Exceptions:

RDBErr error if the number of tokens found does not match the number of tokens expected.

RDBErr error if non-numeric data is found in a numeric column.

RDBErr error if a floating point number is being assigned to an integer column.

S *

Returns:

RDB::Status indicating if end of file, end of line, or end of group was reached.

Reads, parses, and stores data from the next line in the **RDB** file if an input stream has been provided. If **RDB::_autoidx** is set, this method will advance the indices in each **RDBColumn**'s data pointer before reading and will increment the row number, **RDB::_rownum**, for the default '_NR' column.

Definition at line 589 of file **RDB.cc**.

References **_autoidx**, **_cols**, **_filename**, **_firstread**, **_isptr**, **_lastread**, **_line**, **_mode**, **_ncols**, **_rownum**, **advanceIdx()**, **RDBColumn::advanceIdx()**, **RDBColumn::newGroup()**, and **RDBColumn::setData()**.

Referenced by **simpleRDBTable< Type >::readRow()**.

10.1.4.7 bool RDB::write (void) throw (RDBErr)

Write a line of data to the ostream.

Returns:

false if EOF or if the ostream is bad.

Writes the next line of data to the **RDB** file, if an output stream has been provided. If the **RDB** header has not been written yet, it outputs the comments, column names and column definitions. If **RDB::_autoidx** is set, it will advance the indices in the **RDBColumn**'s data pointer before reading and will increment the row number, **RDB::_rownum**, for the default '_NR' column.

After a successful write, the **RDB::_autoidx** flag is set to true.

Definition at line 712 of file **RDB.cc**.

References **_autoidx**, **_cols**, **_comms**, **_mode**, **_ncols**, **_ncomms**, **_osptr**, **_rewindto**, **_rownum**, **_writehdr**, **advanceIdx()**, **RDBColumn::getDef()**, **getDef()**, **RDBColumn::getName()**, and **getName()**.

10.1.4.8 **bool RDB::rewind (void) throw (RDBErr)**

Rewind the stream to the beginning of the first row of data.

Returns:

false if the stream associated with this [RDB](#) object cannot be rewound, i.e seekg() or seekp() is not defined.

Rewinds the stream associate with this object to the beginning of the first row of data. It also calls [RDBColumn::rewind\(void\)](#) for each [RDBColumn](#). If the user supplied data storage to a particular column, the auto-incrementing index is rewound to point at the first element of the user supplied array.

Warning:

If an istream or ostream, like cin or cout, was provided to the object, you only get one chance to read it. You can't rewind, you can't close and reopen.

Definition at line 772 of file RDB.cc.

References [_cols](#), [_isptr](#), [_mode](#), [_ncols](#), [_osptr](#), [_rewindto](#), [_rownum](#), and [RDBColumn::rewind\(\)](#).

10.1.4.9 **bool RDB::autoIdx (void) const**

Indicates if auto-indexing is activated.

Returns:

State of the auto-indexing flag for this object.

Definition at line 843 of file RDB.cc.

References [_autoidx](#).

10.1.4.10 **void RDB::autoIdx (const bool *on*)**

Activates/deactivates auto-indexing.

Parameters:

on sets the auto-indexing behavior for the [RDB](#) object and its columns.

Sets [RDBTable::_autoidx](#). This effectly turns off the auto-incrementing behavior for a single call to [RDB::read\(void\)](#) or [RDB::write\(void\)](#). For arrays of mapped memory, this will cause one line's data to overwrite the previous line's data.

Warning:

`RDB::_autoidx` is set to true after each call to `RDB::read(void)` or `RDB::write(void)`.

Definition at line 830 of file `RDB.cc`.

References `_autoidx`.

10.1.4.11 void RDB::advanceIdx (void)

Increments the indices in the `RDBColumn` data elements.

This method advances the auto-indices for all `RDBColumns` associated with this object.

Definition at line 857 of file `RDB.cc`.

References `_cols`, `_ncols`, `_nrcol`, `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::advanceIdx()`, and `RDBColumn::advanceIdx()`.

Referenced by `read()`, and `write()`.

10.1.4.12 void RDB::setGroup (const string & name, bool group = true) throw (RDBErr)

Turn on/off group status for the named column.

Parameters:

group a bool indicating whether group is on or off.

name the name of the column in this `RDB` object.

Exceptions:

RDBErr error if there is no column with matching name.

Definition at line 878 of file `RDB.cc`.

References `_autoidx`, `_cols`, `_filename`, `_ncols`, `_nrcol`, `getName()`, `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::setGroup()`, and `RDBColumn::setGroup()`.

10.1.4.13 void RDB::setGroup (const int idx, bool group = true) throw (RDBErr)

Turn on/off group status for the indexed column.

Parameters:

group a bool indicating whether group is on or off.

idx the position of the column on which to operate.

Exceptions:

RDBErr error if there is no column with matching name.

Definition at line 911 of file RDB.cc.

References `_autoidx`, `_cols`, `_filename`, `_ncols`, and `RDBColumn::setGroup()`.

10.1.4.14 bool RDB::getGroup (const string & name) throw (RDBErr)

Returns group status, true if its a new group, for the named column.

Parameters:

name the name of the column.

Exceptions:

RDBErrNotFnd error if there is no column with matching name.

Returns:

Status of the column's group flag.

Definition at line 938 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, `RDBColumn::getGroup()`, and `getName()`.

10.1.4.15 bool RDB::getGroup (const int idx) throw (RDBErr)

Returns group status, true if its a new group, for the indexed column.

Parameters:

idx the column index.

Exceptions:

RDBErr error if the index is out of range.

Returns:

Status of the column's group flag.

Definition at line 967 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, and `RDBColumn::getGroup()`.

10.1.4.16 bool RDB::newGroup (void)

Checks if any column indicates a new group.

Returns:

True if any column indicates a new group, false otherwise.

A new group occurs when the data values between consecutive rows change.

Definition at line 989 of file RDB.cc.

References `_cols`, and `_ncols`.

Referenced by `parseLine()`.

10.1.4.17 void RDB::setComment (const string & *comm*, const int *idx* = -1)

Add [RDBComment](#) in header of [RDB](#) object.

Parameters:

comm a comment string.

idx the position of the comment on which to operate.

Comments are numbered as they appear in the [RDB](#) file from top to bottom. If the index is not specified or does not fall within the range of existing comments, the [RDB-Comment](#) is appended to the list of comments.

Definition at line 1015 of file RDB.cc.

References `_comms`, and `_ncomms`.

Referenced by `parseHeader()`, and `setComment()`.

10.1.4.18 void RDB::setComment (RDBComment & *comm*, const int *idx* = -1)

Add or replace [RDBComment](#) in header of [RDB](#) object.

Parameters:

comm a reference to the [RDBComment](#) object

idx the position of the comment on which to operate.

Comments are numbered as they appear in the [RDB](#) file from top to bottom. If the index is not specified or does not fall within the range of existing comments, the [RDB-Comment](#) is appended to the list of comments.

Definition at line 1053 of file RDB.cc.

References `_comms`, and `_ncomms`.

10.1.4.19 void RDB::setComment (RDBComment & *comm*, const string & *name*, const size_t *idx* = 0)

Add or replace [RDBComment](#) in header of [RDB](#) object.

Parameters:

comm a reference to the [RDBComment](#) object

name the name of the comment keyword.

idx currently not defined.

If no matching comment keyword is found, the comment is appended to the list of comments. Otherwise, *comm* replaces the existing comment.

Definition at line 1090 of file RDB.cc.

References `_comms`, `_ncomms`, and `setComment()`.

10.1.4.20 void RDB::setComment (const RDB & *rdb*)

Copy all comments from an existing [RDB](#) object.

Parameters:

rdb a reference to an [RDB](#) object

Copies all comments from the argument to this [RDB](#) object. Any comments previously associated with this object are removed.

Definition at line 1116 of file RDB.cc.

References `_comms`, and `_ncomms`.

10.1.4.21 RDBComment & RDB::getComment (const size_t *idx*) throw (RDBErr)

Return [RDBComment](#) at given index.

Parameters:

idx the index of the [RDBComment](#).

Exceptions:

RDBErrNot error if the index is out of range.

Returns:

[RDBComment](#) with index equal to *idx*.

RDBComments are indexed in the order in which they appear in the [RDB](#) file starting with 0. Parameter *idx* must be between 0 and [RDB::nComments\(void\)](#) less one.

Definition at line 1148 of file [RDB.cc](#).

References [_comms](#), [_filename](#), and [_ncomms](#).

10.1.4.22 RDBComment & RDB::getComment (const string & *name*, const size_t *idx* = 0) throw (RDBErr)

Return [RDBComment](#) with given keyword.

Parameters:

name the name of the comment keyword.

idx currently not defined.

Exceptions:

[RDBErr](#) error if there is no comment with matching keyword.

Returns:

[RDBComment](#) with matching keyword.

Definition at line 1173 of file [RDB.cc](#).

References [_comms](#), [_filename](#), and [_ncomms](#).

10.1.4.23 void RDB::setColumn (const string & *name*, const string & *def*, const int *idx* = -1)

Add an [RDBColumn](#) in [RDB](#) object.

Parameters:

name of the [RDBColumn](#) object

def definition of the [RDBColumn](#) object

idx the position of the column on which to operate.

Columns are numbered as they appear in the [RDB](#) file from left to right starting with 0. If the index is not specified or does not fall within the range of existing columns, an [RDBColumn](#) is created and is appended to the list of columns. The [RDB](#) object handles memory allocation and deletion.

Upon completion, the [RDB](#) object contains a pointer to the [RDBColumn](#) created. Any modifications to the [RDBColumn](#) outside of the [RDB](#) object will be reflected within the [RDB](#) object and vice versa.

Definition at line 1208 of file RDB.cc.

References `_cols`, `_mycols`, `_ncols`, `RDBColumn::setDef()`, and `RDBColumn::setName()`.

Referenced by `setColumn()`.

10.1.4.24 void RDB::setColumn (RDBColumn * *col*, const int *idx* = -1)

Add or replace [RDBColumn](#) in [RDB](#) object.

Parameters:

col a reference to the [RDBColumn](#) object

idx the position of the column on which to operate.

Columns are numbered as they appear in the [RDB](#) file from left to right starting with 0. If the index is not specified or does not fall within the range of existing columns, the [RDBColumn](#) is appended to the list of columns.

Upon completion, the [RDB](#) object contains a pointer to the [RDBColumn](#) provided. Any modifications to the [RDBColumn](#) outside of the [RDB](#) object will be reflected within the [RDB](#) object and vice versa.

Warning:

The user is responsible for freeing the [RDBColumn](#).

Definition at line 1274 of file RDB.cc.

References `_cols`, `_mycols`, and `_ncols`.

10.1.4.25 void RDB::setColumn (RDBColumn * *col*, const string & *name*, const size_t *idx* = 0)

Add or replace [RDBColumn](#) in [RDB](#) object.

Parameters:

col a reference to the [RDBColumn](#) object

name the name of the column in this [RDB](#) object.

idx currently not defined.

If no matching column is found, the column is appended to the list of columns after assigning it a name of '*name*'. Otherwise, *col* replaces the existing column.

Upon completion, the [RDB](#) object contains a pointer to the [RDBColumn](#) provided. Any modifications to the [RDBColumn](#) outside of the [RDB](#) object will be reflected within the [RDB](#) object and vice versa.

Warning:

The user is responsible for freeing the [RDBColumn](#).

Definition at line 1331 of file RDB.cc.

References `_cols`, `_mycols`, `_ncols`, `getName()`, `setColumn()`, and `RDBColumn::setName()`.

10.1.4.26 void RDB::setColumn (const RDB & rdb)

Copy all columns from an existing [RDB](#) object.

Parameters:

rdb a reference to an [RDB](#) object

Copies all columns from the argument to this [RDB](#) object. Any columns previously associated with this object are removed.

Warning:

The user is responsible for free any [RDBColumns](#) previously allocated and assigned to this [RDB](#) object via the [RDB::setColumn](#) methods.

Definition at line 1368 of file RDB.cc.

References `_cols`, `_mycols`, and `_ncols`.

10.1.4.27 RDBColumn * RDB::getColumn (const size_t idx) throw (RDBErr)

Return pointer to [RDBColumn](#) at given index.

Parameters:

idx the index of the [RDBColumn](#).

Exceptions:

[RDBErr](#) error if the index is out of range.

Returns:

[RDBColumn](#) with index equal to *idx*.

[RDBColumns](#) are indexed in the order in which they appear in the [RDB](#) file starting with 0. Parameter *idx* must be between 0 and `RDB::nColumns(void)` less one.

Definition at line 1433 of file RDB.cc.

References `_cols`, `_filename`, and `_ncols`.

10.1.4.28 RDBColumn * RDB::getColumn (const string & name, const size_t idx = 0) throw (RDBErr)

Return pointer to [RDBColumn](#) with given name.

Parameters:

name the name of the column.

idx currently not defined.

Exceptions:

RDBErrNotFound error if there is no column with matching name.

Returns:

[RDBColumn](#) with matching name.

Definition at line 1458 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, and `getName()`.

10.1.4.29 void RDB::setName (const size_t idx, const string & name) throw (RDBErr)

Modify the name of the [RDBColumn](#) at idx.

Parameters:

idx index of [RDBColumn](#).

name to assign to [RDBColumn](#) at idx.

Exceptions:

RDBErr if index is out of range.

Definition at line 1488 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, and `RDBColumn::setName()`.

10.1.4.30 void RDB::setDef (const size_t idx, const string & def) throw (RDBErr)

Modify the definition of the [RDBColumn](#) at idx.

Parameters:

idx index of [RDBColumn](#).

def [RDBColumn](#) definition.

Exceptions:

[RDBErr](#) if index is out of range.

[RDBErr](#) if def is invalid [RDBColumn](#) definition.

Definition at line 1509 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, and `RDBColumn::setDef()`.

10.1.4.31 void RDB::setWidth (const size_t *idx*, const long *width*) throw (RDBErr)

Modify the width of the [RDBColumn](#) at *idx*.

Parameters:

idx index of [RDBColumn](#).

width [RDBColumn](#) width.

Exceptions:

[RDBErr](#) if index is out of range.

[RDBErr](#) if width is invalid [RDBColumn](#) width.

Definition at line 1537 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, and `RDBColumn::setWidth()`.

10.1.4.32 void RDB::setType (const size_t *idx*, const RDBColumn::Type *type*) throw (RDBErr)

Modify the type of the [RDBColumn](#) at *idx*.

Parameters:

idx index of [RDBColumn](#).

type [RDBColumn](#) type.

Exceptions:

[RDBErr](#) if index is out of range.

[RDBErr](#) if type is invalid [RDBColumn](#) type.

Definition at line 1565 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, and `RDBColumn::setType()`.

10.1.4.33 `void RDB::setJust (const size_t idx, const RDBColumn::Just just) throw (RDBErr)`

Modify the justification of the [RDBColumn](#) at *idx*.

Parameters:

idx index of [RDBColumn](#).
just [RDBColumn](#) justification.

Exceptions:

[RDBErr](#) if index is out of range.
[RDBErr](#) if just is invalid [RDBColumn](#) justification.

Definition at line 1593 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, and `RDBColumn::setJust()`.

10.1.4.34 `void RDB::setDesc (const size_t idx, const string & desc) throw (RDBErr)`

Modify the description of the [RDBColumn](#) at *idx*.

Parameters:

idx index of [RDBColumn](#).
desc [RDBColumn](#) description.

Exceptions:

[RDBErr](#) if index is out of range.
[RDBErr](#) if desc is invalid [RDBColumn](#) description.

Definition at line 1621 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, and `RDBColumn::setDesc()`.

10.1.4.35 `void RDB::mapData (const size_t idx, double data[], const size_t nelems = 1) throw (RDBErr)`

Map [RDBColumn](#) data to user-supplied memory.

Parameters:

idx index of [RDBColumn](#).
data user-supplied memory for storing data.

nelems number of elements in user-supplied data.

Exceptions:

RDBErr if index is out of range.

RDBErr if data is invalid datatype for [RDBColumn](#).

Definition at line 1650 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), and [RDBColumn::mapData\(\)](#).

10.1.4.36 void RDB::mapData (const size_t *idx*, long *data*[], const size_t *nelems* = 1) throw (*RDBErr***)**

Map [RDBColumn](#) data to user-supplied memory.

Parameters:

idx index of [RDBColumn](#).

data user-supplied memory to stored data.

nelems number of elems in user-supplied memory.

Exceptions:

RDBErr if index is out of range.

RDBErr if data is invalid datatype for [RDBColumn](#).

Definition at line 1678 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), and [RDBColumn::mapData\(\)](#).

10.1.4.37 void RDB::mapData (const size_t *idx*, string *data*[], const size_t *nelems* = 1) throw (*RDBErr***)**

Map [RDBColumn](#) data to user-supplied memory.

Parameters:

idx index of [RDBColumn](#).

data user-supplied memory to store data.

nelems number of elements in user-supplied data.

Exceptions:

RDBErr if index is out of range.

RDBErr if data is invalid datatype for [RDBColumn](#).

Definition at line 1707 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), and [RDBColumn::mapData\(\)](#).

10.1.4.38 void RDB::setData (const size_t *idx*, const double *data*) throw (RDBErr)

Sets the data value of [RDBColumn](#), converting as necessary.

Parameters:

idx index of [RDBColumn](#).

data value to assign to [RDBColumn](#) data.

Exceptions:

RDBErr if index is out of range.

RDBErr if data is invalid for [RDBColumn](#).

Definition at line 1735 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), and [RDBColumn::setData\(\)](#).

10.1.4.39 void RDB::setData (const size_t *idx*, const long *data*) throw (RDBErr)

Sets the data value of [RDBColumn](#), converting as necessary.

Parameters:

idx index of [RDBColumn](#).

data value to assign to [RDBColumn](#) data.

Exceptions:

RDBErr if index is out of range.

RDBErr if data is invalid for [RDBColumn](#).

Definition at line 1763 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), and [RDBColumn::setData\(\)](#).

10.1.4.40 void RDB::setData (const size_t *idx*, const string & *data*) throw (RDBErr)

Sets the data value of [RDBColumn](#), converting as necessary.

Parameters:

idx index of [RDBColumn](#)/
data value to assign [RDBColumn](#) data.

Exceptions:

[RDBErr](#) if index is out of range.
[RDBErr](#) if data is invalid for [RDBColumn](#).

Definition at line 1791 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), and [RDBColumn::setData\(\)](#).

10.1.4.41 void RDB::getName (const size_t *idx*, string & *name*) const throw (RDBErr)

Return the name of the [RDBColumn](#) at *idx*.

Parameters:

idx index of [RDBColumn](#).
name retrieve name of [RDBColumn](#).

Exceptions:

[RDBErr](#) if index is out of range.

Definition at line 1818 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), and [RDBColumn::getName\(\)](#).

Referenced by [close\(\)](#), [getColumn\(\)](#), [getData\(\)](#), [getDataDouble\(\)](#), [getDataLong\(\)](#), [getDataString\(\)](#), [getDef\(\)](#), [getDesc\(\)](#), [getGroup\(\)](#), [getJust\(\)](#), [getName\(\)](#), [getType\(\)](#), [getWidth\(\)](#), [mapData\(\)](#), [setColumn\(\)](#), [setData\(\)](#), [setDef\(\)](#), [setDesc\(\)](#), [setGroup\(\)](#), [setJust\(\)](#), [setName\(\)](#), [setType\(\)](#), [setWidth\(\)](#), and [write\(\)](#).

10.1.4.42 void RDB::getDef (const size_t *idx*, string & *def*) throw (RDBErr)

Return the definition of the [RDBColumn](#) at *idx*.

Parameters:

idx index of [RDBColumn](#).

def retrieve definition of [RDBColumn](#).

Exceptions:

[RDBErr](#) if index is out of range.

Definition at line 1837 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), and [RDBColumn::getDef\(\)](#).

Referenced by [close\(\)](#), and [write\(\)](#).

10.1.4.43 void RDB::getWidth (const size_t *idx*, long & *width*) const throw (RDBErr)

Return the width of the [RDBColumn](#) at *idx*.

Parameters:

idx index of [RDBColumn](#).

width retrieve width of [RDBColumn](#).

Exceptions:

[RDBErr](#) if index is out of range.

Definition at line 1856 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), and [RDBColumn::getWidth\(\)](#).

10.1.4.44 void RDB::getType (const size_t *idx*, RDBColumn::Type & *type*) const throw (RDBErr)

Return the type of the [RDBColumn](#) at *idx*.

Parameters:

idx index of [RDBColumn](#).

type retrieve type of [RDBColumn](#).

Exceptions:

[RDBErr](#) if index is out of range.

Definition at line 1875 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), and [RDBColumn::getType\(\)](#).

10.1.4.45 void RDB::getJust (const size_t *idx*, RDBColumn::Just & *just*) const throw (RDBErr)

Return the just of the [RDBColumn](#) at *idx*.

Parameters:

idx index of [RDBColumn](#)
just retrieve just of [RDBColumn](#).

Exceptions:

[RDBErr](#) if index is out of range.

Definition at line 1894 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, and `RDBColumn::getJust()`.

10.1.4.46 void RDB::getDesc (const size_t *idx*, string & *desc*) const throw (RDBErr)

Return the description of the [RDBColumn](#) at *idx*.

Parameters:

idx index of [RDBColumn](#)
desc retrieve description of [RDBColumn](#).

Exceptions:

[RDBErr](#) if index is out of range.

Definition at line 1913 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, and `RDBColumn::getDesc()`.

10.1.4.47 void RDB::getData (const size_t *idx*, double & *data*) throw (RDBErr)

Return the data of the [RDBColumn](#) at *idx*, converting if necessary.

Parameters:

idx index of [RDBColumn](#)
data retrieve data of [RDBColumn](#).

Exceptions:

[RDBErr](#) if index is out of range.

RDBErr if data is invalid datatype for [RDBColumn](#).

Definition at line 1933 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, and `RDBColumn::getDataDouble()`.

10.1.4.48 void RDB::getData (const size_t *idx*, long & *data*) throw (RDBErr)

Return the data of the [RDBColumn](#) at *idx*, converting if necessary.

Parameters:

idx index of [RDBColumn](#)

data retrieve data of [RDBColumn](#).

Exceptions:

RDBErr if index is out of range.

RDBErr if data is invalid datatype for [RDBColumn](#).

Definition at line 1961 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, and `RDBColumn::getDataLong()`.

10.1.4.49 void RDB::getData (const size_t *idx*, string & *data*) throw (RDBErr)

Return the data of the [RDBColumn](#) at *idx*, converting if necessary.

Parameters:

idx index of [RDBColumn](#)

data retrieve data of [RDBColumn](#).

Exceptions:

RDBErr if index is out of range.

RDBErr if data is invalid datatype for [RDBColumn](#).

Definition at line 1989 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, and `RDBColumn::getDataString()`.

10.1.4.50 string RDB::getName (const size_t *idx*) const throw (RDBErr)

Return the name of the [RDBColumn](#) at *idx*.

Parameters:

idx index of [RDBColumn](#)

Exceptions:

[RDBErr](#) if index is out of range.

Returns:

name of [RDBColumn](#).

Definition at line 2017 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, and `RDBColumn::getName()`.

10.1.4.51 string RDB::getDef (const size_t *idx*) throw (RDBErr)

Return the definition of the [RDBColumn](#) at *idx*.

Parameters:

idx index of [RDBColumn](#)

Exceptions:

[RDBErr](#) if index is out of range.

Returns:

definition of [RDBColumn](#).

Definition at line 2037 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, and `RDBColumn::getDef()`.

10.1.4.52 long RDB::getWidth (const size_t *idx*) const throw (RDBErr)

Return the width of the [RDBColumn](#) at *idx*.

Parameters:

idx index of [RDBColumn](#)

Exceptions:

[RDBErr](#) if index is out of range.

Returns:

width of [RDBColumn](#).

Definition at line 2057 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), and [RDBColumn::getWidth\(\)](#).

10.1.4.53 RDBColumn::Type RDB::getType (const size_t *idx*) const throw (RDBErr)

Return the type of the [RDBColumn](#) at *idx*.

Parameters:

idx index of [RDBColumn](#)

Exceptions:

[RDBErr](#) if index is out of range.

Returns:

type of [RDBColumn](#).

Definition at line 2077 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), and [RDBColumn::getType\(\)](#).

10.1.4.54 RDBColumn::Just RDB::getJust (const size_t *idx*) const throw (RDBErr)

Return the justification of the [RDBColumn](#) at *idx*.

Parameters:

idx index of [RDBColumn](#)

Exceptions:

[RDBErr](#) if index is out of range.

Returns:

justification of [RDBColumn](#).

Definition at line 2097 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), and [RDBColumn::getJust\(\)](#).

10.1.4.55 string RDB::getDesc (const size_t *idx*) const throw (RDBErr)

Return the description of the [RDBColumn](#) at *idx*.

Parameters:

idx index of [RDBColumn](#)

Exceptions:

[RDBErr](#) if index is out of range.

Returns:

description of [RDBColumn](#).

Definition at line 2117 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, and `RDBColumn::getDesc()`.

10.1.4.56 double RDB::getDataDouble (const size_t *idx*) throw (RDBErr)

Return the data of the [RDBColumn](#) at *idx*, converting if necessary.

Parameters:

idx index of [RDBColumn](#)

Exceptions:

[RDBErr](#) if index is out of range.

[RDBErr](#) if data is invalid datatype for [RDBColumn](#).

Returns:

data of [RDBColumn](#).

Definition at line 2138 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, and `RDBColumn::getDataDouble()`.

10.1.4.57 long RDB::getDataLong (const size_t *idx*) throw (RDBErr)

Return the data of the [RDBColumn](#) at *idx*, converting if necessary.

Parameters:

idx index of [RDBColumn](#)

Exceptions:

RDBErr if index is out of range.

RDBErr if data is invalid datatype for [RDBColumn](#).

Returns:

Data of [RDBColumn](#).

Definition at line 2167 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, and `RDBColumn::getDataLong()`.

10.1.4.58 string RDB::getDataString (const size_t *idx*) throw (RDBErr)

Return the data of the [RDBColumn](#) at *idx*, converting if necessary.

Parameters:

idx index of [RDBColumn](#)

Exceptions:

RDBErr if index is out of range.

RDBErr if data is invalid datatype for [RDBColumn](#).

Returns:

data of [RDBColumn](#).

Definition at line 2196 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, and `RDBColumn::getDataString()`.

10.1.4.59 void RDB::setName (const string & *name*, const string & *newname*) throw (RDBErr)

Modify the [RDBColumn](#) name.

Parameters:

name of [RDBColumn](#)

newname new name of [RDBColumn](#).

Exceptions:

RDBErr if no matching column name is found.

RDBErr if newname is invalid name for [RDBColumn](#).

Definition at line 2224 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, `getName()`, and `RDBColumn::setName()`.

10.1.4.60 `void RDB::setDef (const string & name, const string & def) throw (RDBErr)`

Modify the [RDBColumn](#) definition.

Parameters:

name of [RDBColumn](#)
def definition of [RDBColumn](#).

Exceptions:

[RDBErr](#) if no matching column name is found.
[RDBErr](#) if def is invalid definition for [RDBColumn](#).

Definition at line 2250 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, `getName()`, and `RDBColumn::setDef()`.

10.1.4.61 `void RDB::setWidth (const string & name, const long width) throw (RDBErr)`

Modify the [RDBColumn](#) width.

Parameters:

name of [RDBColumn](#)
width width of [RDBColumn](#).

Exceptions:

[RDBErr](#) if no matching column name is found.
[RDBErr](#) if width is invalid width for [RDBColumn](#).

Definition at line 2285 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, `getName()`, and `RDBColumn::setWidth()`.

10.1.4.62 void RDB::setType (const string & *name*, const RDBColumn::Type *type*) throw (RDBErr)

Modify the [RDBColumn](#) type.

Parameters:

name of [RDBColumn](#)
type type of [RDBColumn](#).

Exceptions:

[RDBErr](#) if no matching column name is found.
[RDBErr](#) if type is invalid type for [RDBColumn](#).

Definition at line 2320 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), [_nrcol](#), [getName\(\)](#), and [RDBColumn::setType\(\)](#).

10.1.4.63 void RDB::setJust (const string & *name*, const RDBColumn::Just *just*) throw (RDBErr)

Modify the [RDBColumn](#) justification.

Parameters:

name of [RDBColumn](#)
just justification of [RDBColumn](#).

Exceptions:

[RDBErr](#) if no matching column name is found.
[RDBErr](#) if just is invalid justification for [RDBColumn](#).

Definition at line 2355 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), [_nrcol](#), [getName\(\)](#), and [RDBColumn::setJust\(\)](#).

10.1.4.64 void RDB::setDesc (const string & *name*, const string & *desc*) throw (RDBErr)

Modify the [RDBColumn](#) description.

Parameters:

name of [RDBColumn](#)
desc description of [RDBColumn](#).

Exceptions:

RDBErr if no matching column name is found.

RDBErr if desc is invalid description for [RDBColumn](#).

Definition at line 2390 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, `getName()`, and `RDBColumn::setDesc()`.

10.1.4.65 void RDB::mapData (const string & name, double data[], const size_t nelems = 1) throw (RDBErr)

Map RDBColumn data to user-supplied memory.

Parameters:

name of [RDBColumn](#)

data user-supplied memory to store [RDBColumn](#) data.

nelems number of elems in user-supplied memory.

Exceptions:

RDBErr if no matching column name is found.

RDBErr if data is invalid datatype for [RDBColumn](#).

Definition at line 2426 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `getName()`, and `RDBColumn::mapData()`.

10.1.4.66 void RDB::mapData (const string & name, long data[], const size_t nelems = 1) throw (RDBErr)

Map RDBColumn data to user-supplied memory.

Parameters:

name of [RDBColumn](#)

data user-supplied memory to store [RDBColumn](#) data.

nelems number of elems in user-supplied memory.

Exceptions:

RDBErr if no matching column name is found.

RDBErr if data is invalid datatype for [RDBColumn](#).

Definition at line 2462 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, `getName()`, `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::mapData()`, and `RDBColumn::mapData()`.

10.1.4.67 `void RDB::mapData (const string & name, string data[], const size_t nelems = 1) throw (RDBErr)`

Map RDBColumn data to user-supplied memory.

Parameters:

name of [RDBColumn](#)

data user-supplied memory to store [RDBColumn](#) data.

nelems number of elems in user-supplied memory.

Exceptions:

[RDBErr](#) if no matching column name is found.

[RDBErr](#) if data is invalid datatype for [RDBColumn](#).

Definition at line 2499 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `getName()`, and `RDBColumn::mapData()`.

10.1.4.68 `void RDB::setData (const string & name, const double data) throw (RDBErr)`

Modify the [RDBColumn](#) data, converting if necessary.

Parameters:

name of [RDBColumn](#)

data value to assign [RDBColumn](#) data.

Exceptions:

[RDBErr](#) if no matching column name is found.

[RDBErr](#) if data is invalid datatype for [RDBColumn](#).

Definition at line 2534 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, `getName()`, `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::setData()`, and `RDBColumn::setData()`.

10.1.4.69 `void RDB::setData (const string & name, const long data) throw (RDBErr)`

Modify the [RDBColumn](#) data, converting if necessary.

Parameters:

name of [RDBColumn](#)

data value to assign [RDBColumn](#) data.

Exceptions:

[*RDBErr*](#) if no matching column name is found.

[*RDBErr*](#) if data is invalid datatype for [RDBColumn](#).

Definition at line 2567 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), [_nrcol](#), [getName\(\)](#), [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::setData\(\)](#), and [RDBColumn::setData\(\)](#).

10.1.4.70 void RDB::setData (const string & name, const string & data) throw (RDBErr)

Modify the [RDBColumn](#) data, converting if necessary.

Parameters:

name of [RDBColumn](#)

data value to assign [RDBColumn](#) data.

Exceptions:

[*RDBErr*](#) if no matching column name is found.

[*RDBErr*](#) if data is invalid datatype for [RDBColumn](#).

Definition at line 2600 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), [_nrcol](#), [getName\(\)](#), [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::setData\(\)](#), and [RDBColumn::setData\(\)](#).

10.1.4.71 void RDB::getName (const string & name, string & namefound) const throw (RDBErr)

Return the name of the [RDBColumn](#).

Parameters:

name of [RDBColumn](#)

namefound name of [RDBColumn](#) if found.

Exceptions:

[*RDBErr*](#) if no matching column name is found.

Definition at line 2633 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), [_nrcol](#), [RDBColumn::getName\(\)](#), and [getName\(\)](#).

10.1.4.72 void RDB::getDef (const string & *name*, string & *def*) throw (RDBErr)

Return the definition of the [RDBColumn](#).

Parameters:

name of [RDBColumn](#)

def definition of [RDBColumn](#).

Exceptions:

[RDBErr](#) if no matching column name is found.

Definition at line 2657 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, [RDBColumn::getDef\(\)](#), and [getName\(\)](#).

10.1.4.73 void RDB::getWidth (const string & *name*, long & *width*) const throw (RDBErr)

Return the width of the [RDBColumn](#).

Parameters:

name of [RDBColumn](#)

width width of [RDBColumn](#).

Exceptions:

[RDBErr](#) if no matching column name is found.

Definition at line 2681 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, [getName\(\)](#), and [RDBColumn::getWidth\(\)](#).

10.1.4.74 void RDB::getType (const string & *name*, RDBColumn::Type & *type*) const throw (RDBErr)

Return the type of the [RDBColumn](#).

Parameters:

name of [RDBColumn](#)

type type of [RDBColumn](#).

Exceptions:

RDBErr if no matching column name is found.

Definition at line 2705 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, `getName()`, and `RDBColumn::getType()`.

10.1.4.75 void RDB::getJust (const string & name, RDBColumn::Just & just) const throw (RDBErr)

Return the justification of the [RDBColumn](#).

Parameters:

name of [RDBColumn](#)

just justification of [RDBColumn](#).

Exceptions:

RDBErr if no matching column name is found.

Definition at line 2729 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, `RDBColumn::getJust()`, and `getName()`.

10.1.4.76 void RDB::getDesc (const string & name, string & desc) const throw (RDBErr)

Return the description of the [RDBColumn](#).

Parameters:

name of [RDBColumn](#)

desc description of [RDBColumn](#).

Exceptions:

RDBErr if no matching column name is found.

Definition at line 2753 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, `RDBColumn::getDesc()`, and `getName()`.

10.1.4.77 void RDB::getData (const string & name, double & data) throw (RDBErr)

Return the data of the [RDBColumn](#), converting if necessary.

Parameters:

name of [RDBColumn](#)
data data of [RDBColumn](#).

Exceptions:

[RDBErr](#) if no matching column name is found.
[RDBErr](#) if data is invalid datatype for [RDBColumn](#).

Definition at line 2778 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), [_nrcol](#), [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getDataDouble\(\)](#), [RDBColumn::getDataDouble\(\)](#), and [getName\(\)](#).

10.1.4.78 void RDB::getData (const string & name, long & data) throw (RDBErr)

Return the data of the [RDBColumn](#), converting if necessary.

Parameters:

name of [RDBColumn](#)
data data of [RDBColumn](#).

Exceptions:

[RDBErr](#) if no matching column name is found.
[RDBErr](#) if data is invalid datatype for [RDBColumn](#).

Definition at line 2812 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), [_nrcol](#), [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getDataLong\(\)](#), [RDBColumn::getDataLong\(\)](#), and [getName\(\)](#).

10.1.4.79 void RDB::getData (const string & name, string & data) throw (RDBErr)

Return the data of the [RDBColumn](#), converting if necessary.

Parameters:

name of [RDBColumn](#)
data data of [RDBColumn](#).

Exceptions:

[RDBErr](#) if data is invalid datatype for [RDBColumn](#).

RDBErr if no matching column name is found.

Definition at line 2846 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getDataString()`, `RDBColumn::getDataString()`, and `getName()`.

10.1.4.80 `string RDB::getName (const string & name) const throw (RDBErr)`

Return the name of the [RDBColumn](#).

Parameters:

name of [RDBColumn](#)

Exceptions:

RDBErr if no matching column name is found.

Returns:

name of [RDBColumn](#).

Definition at line 2880 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, `RDBColumn::getName()`, and `getName()`.

10.1.4.81 `string RDB::getDef (const string & name) throw (RDBErr)`

Return the definition of the [RDBColumn](#).

Parameters:

name of [RDBColumn](#)

Exceptions:

RDBErr if no matching column name is found.

Returns:

definition of [RDBColumn](#).

Definition at line 2904 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, `RDBColumn::getDef()`, and `getName()`.

10.1.4.82 long RDB::getWidth (const string & *name*) const throw (RDBErr)

Return the width of the [RDBColumn](#).

Parameters:

name of [RDBColumn](#)

Exceptions:

[RDBErr](#) if no matching column name is found.

Returns:

width of [RDBColumn](#).

Definition at line 2928 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), [_nrcol](#), [getName\(\)](#), and [RDBColumn::getWidth\(\)](#).

10.1.4.83 RDBColumn::Type RDB::getType (const string & *name*) const throw (RDBErr)

Return the type of the [RDBColumn](#).

Parameters:

name of [RDBColumn](#)

Exceptions:

[RDBErr](#) if no matching column name is found.

Returns:

type of [RDBColumn](#).

Definition at line 2952 of file RDB.cc.

References [_cols](#), [_filename](#), [_ncols](#), [_nrcol](#), [getName\(\)](#), and [RDBColumn::getType\(\)](#).

10.1.4.84 RDBColumn::Just RDB::getJust (const string & *name*) const throw (RDBErr)

Return the justification of the [RDBColumn](#).

Parameters:

name of [RDBColumn](#)

Exceptions:

RDBErr if no matching column name is found.

Returns:

justification of [RDBColumn](#).

Definition at line 2976 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, `RDBColumn::getJust()`, and `getName()`.

10.1.4.85 string RDB::getDesc (const string & name) const throw (RDBErr)

Return the description of the [RDBColumn](#).

Parameters:

name of [RDBColumn](#)

Exceptions:

RDBErr if no matching column name is found.

Returns:

description of [RDBColumn](#).

Definition at line 3000 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, `RDBColumn::getDesc()`, and `getName()`.

10.1.4.86 double RDB::getDataDouble (const string & name) throw (RDBErr)

Return the data of the [RDBColumn](#), converting if necessary.

Parameters:

name of [RDBColumn](#)

Exceptions:

RDBErr if no matching column name is found.

RDBErr if data is invalid datatype for [RDBColumn](#).

Returns:

data of [RDBColumn](#).

Definition at line 3025 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getDataDouble()`, `RDBColumn::getDataDouble()`, and `getName()`.

10.1.4.87 `long RDB::getDataLong (const string & name) throw (RDBErr)`

Return the data of the [RDBColumn](#), converting if necessary.

Parameters:

name of [RDBColumn](#)

Exceptions:

[RDBErr](#) if no matching column name is found.

[RDBErr](#) if data is invalid datatype for [RDBColumn](#).

Returns:

data of [RDBColumn](#).

Definition at line 3058 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getDataLong()`, `RDBColumn::getDataLong()`, and `getName()`.

10.1.4.88 `string RDB::getDataString (const string & name) throw (RDBErr)`

Return the data of the [RDBColumn](#), converting if necessary.

Parameters:

name of [RDBColumn](#)

Exceptions:

[RDBErr](#) if no matching column name is found.

[RDBErr](#) if data is invalid datatype for [RDBColumn](#).

Returns:

data of [RDBColumn](#).

Definition at line 3091 of file RDB.cc.

References `_cols`, `_filename`, `_ncols`, `_nrcol`, `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getDataString()`, `RDBColumn::getDataString()`, and `getName()`.

10.1.4.89 size_t RDB::nComments (void) const

Return number of comments in [RDB](#) object.

Returns:

Number of comments.

Definition at line 3120 of file RDB.cc.

References `_ncomms`.

10.1.4.90 size_t RDB::nColumns (void) const

Return number of columns in [RDB](#) object.

Returns:

Number of columns.

Definition at line 3133 of file RDB.cc.

References `_ncols`.

10.1.4.91 size_t RDB::nRows (void)

Return number of rows in [RDB](#) object.

Returns:

Number of rows.

Warning:

This method reads through the entire [RDB](#) file to count the number of rows and then attempts to rewind the file to the location at which it began . If the stream attached to the [RDB](#) object is not seekable, this method will fail.

Definition at line 3151 of file RDB.cc.

References `_isptr`, `_knowrows`, `_line`, `_mode`, `_nrows`, and `_rewindto`.

10.1.4.92 void RDB::parseHeader (void) throw (RDBErr) [protected]

Parse header, i.e. comments and column names and definitions.

Parses out comments and column names and definitions from the [RDB](#) file header. This is used by [RDB::open\(\)](#).

Definition at line 3185 of file RDB.cc.

References `_cols`, `_isptr`, `_mycols`, `_ncols`, `_ncomms`, `_nrows`, `_rewindto`, `_rownum`, and `setComment()`.

Referenced by `open()`.

10.1.4.93 `vector< string > RDB::parseLine (const string & line) const`
[protected]

Parse fields in a row.

Parameters:

line the line to be split.

Returns:

Vector of tokens, one for each tab delimited field.

Splits the input line on tabs.

Definition at line 3284 of file RDB.cc.

10.1.4.94 `size_t RDB::parseLine (bool & newgroup) throw (RDBErr)`
[protected]

Parse fields in a row.

Returns:

number of tokens parsed.

Splits the line on tabs and assigns the tokens to the `RDBCColumns`.

Definition at line 3316 of file RDB.cc.

References `_cols`, `_line`, `_rownum`, `newGroup()`, and `RDBCColumn::setData()`.

10.1.5 Friends And Related Function Documentation

10.1.5.1 `istream& operator>> (istream & is, RDB & rdb) throw (RDBErr)`
[friend]

Read table from input stream.

Parameters:

is the input stream.

rdb the table to fill.

Returns:

A reference to the input stream.

If the stream contains a valid rdbtable fill it... otherwise set ios::failbit.

Definition at line 38 of file RDB.cc.

10.1.5.2 ostream& operator<< (ostream & os, RDB & rdb) throw (RDBErr)
[friend]

Write table to output stream.

Parameters:

os the output stream.

rdb the table to print.

Returns:

A reference to the output stream

Places the table on the output stream.

Definition at line 76 of file RDB.cc.

10.1.6 Member Data Documentation**10.1.6.1 string RDB::_filename** [protected]

Name of [RDB](#) file.

Definition at line 303 of file RDB.h.

Referenced by close(), getColumn(), getComment(), getData(), getDataDouble(), getDataLong(), getDataString(), getDef(), getDesc(), getGroup(), getJust(), getName(), getType(), getWidth(), mapData(), open(), read(), setData(), setDef(), setDesc(), setGroup(), setJust(), setName(), setType(), and setWidth().

10.1.6.2 ios::openmode RDB::_mode [protected]

Open mode of the associated stream.

Definition at line 305 of file RDB.h.

Referenced by nRows(), open(), read(), rewind(), and write().

10.1.6.3 istream* RDB::_isptr [protected]

Istream attached to data file.

Definition at line 308 of file RDB.h.

Referenced by `close()`, `nRows()`, `open()`, `parseHeader()`, `read()`, `simpleRDBTable<Type>::readRow()`, `rewind()`, and `~RDB()`.

10.1.6.4 ostream* RDB::_osptr [protected]

Ostream attached to data file.

Definition at line 310 of file RDB.h.

Referenced by `close()`, `open()`, `rewind()`, `write()`, and `~RDB()`.

10.1.6.5 bool RDB::_myisptr [protected]

Indicates if [RDB](#) object is responsible for deallocating the istream.

Definition at line 312 of file RDB.h.

Referenced by `close()`, and `open()`.

10.1.6.6 bool RDB::_myosptr [protected]

Indicates if [RDB](#) object is responsible for deallocating the ostream.

Definition at line 314 of file RDB.h.

Referenced by `close()`, and `open()`.

10.1.6.7 size_t RDB::_rewindto [protected]

Position of beginning of first row of data.

Definition at line 317 of file RDB.h.

Referenced by `close()`, `nRows()`, `parseHeader()`, `rewind()`, and `write()`.

10.1.6.8 size_t RDB::_ncomms [protected]

Number of comments.

Definition at line 319 of file RDB.h.

Referenced by `close()`, `getComment()`, `nComments()`, `parseHeader()`, `setComment()`, and `write()`.

10.1.6.9 size_t RDB::_ncols [protected]

Number of columns.

Definition at line 321 of file RDB.h.

Referenced by `advanceIdx()`, `close()`, `getColumn()`, `getData()`, `getDataDouble()`, `getDataLong()`, `getDataString()`, `getDef()`, `getDesc()`, `getGroup()`, `getJust()`, `getName()`, `getType()`, `getWidth()`, `mapData()`, `nColumns()`, `newGroup()`, `parseHeader()`, `read()`, `rewind()`, `setColumn()`, `setData()`, `setDef()`, `setDesc()`, `setGroup()`, `setJust()`, `setName()`, `setType()`, `setWidth()`, `write()`, and `~RDB()`.

10.1.6.10 `size_t RDB::_nrows` [protected]

Number of rows.

Definition at line 323 of file RDB.h.

Referenced by `close()`, `nRows()`, and `parseHeader()`.

10.1.6.11 `bool RDB::_knowrows` [protected]

Indicates if associated file must be scanned to determine number of rows.

Definition at line 325 of file RDB.h.

Referenced by `close()`, and `nRows()`.

10.1.6.12 `long RDB::_rownum` [protected]

Current `*table*` row number.

Definition at line 327 of file RDB.h.

Referenced by `close()`, `parseHeader()`, `parseLine()`, `read()`, `rewind()`, and `write()`.

10.1.6.13 `long RDB::_frownum` [protected]

Current `*file*` row number.

Definition at line 329 of file RDB.h.

10.1.6.14 `bool RDB::_autoidx` [protected]

Indicates if [RDBCColumn](#) data elements should be advanced.

Definition at line 332 of file RDB.h.

Referenced by `autoIdx()`, `close()`, `read()`, `setGroup()`, and `write()`.

10.1.6.15 `bool RDB::_firstread` [protected]

Indicates if this is the first call to [RDB::read](#).

Definition at line 334 of file RDB.h.

Referenced by read().

10.1.6.16 **bool RDB::_lastread** [protected]

Indicates if this is the last call to [RDB::read](#).

Definition at line 336 of file RDB.h.

Referenced by read().

10.1.6.17 **bool RDB::_writehdr** [protected]

Indicates if the header has been output.

Definition at line 338 of file RDB.h.

Referenced by close(), and write().

10.1.6.18 **RDBComment* RDB::_comms** [protected]

Array of RDBComments.

Definition at line 341 of file RDB.h.

Referenced by close(), getComment(), setComment(), write(), and ~RDB().

10.1.6.19 **RDBColumn** RDB::_cols** [protected]

Array of RDBColumns.

Definition at line 343 of file RDB.h.

Referenced by advanceIdx(), close(), getColumn(), getData(), getDataDouble(), getDataLong(), getDataString(), getDef(), getDesc(), getGroup(), getJust(), getName(), getType(), getWidth(), mapData(), newGroup(), parseHeader(), parseLine(), read(), rewind(), setColumn(), setData(), setDef(), setDesc(), setGroup(), setJust(), setName(), setType(), setWidth(), write(), and ~RDB().

10.1.6.20 **RDBLongColumn RDB::_nrcol** [protected]

Hidden column, containing row number.

Definition at line 345 of file RDB.h.

Referenced by advanceIdx(), getColumn(), getData(), getDataDouble(), getDataLong(), getDataString(), getDef(), getDesc(), getGroup(), getJust(), getName(), getType(), getWidth(), mapData(), setData(), setDef(), setDesc(), setGroup(), setJust(), setName(), setType(), and setWidth().

10.1.6.21 `bool* RDB::_mycols` [protected]

Indicates if [RDB](#) object is responsible for deallocating given [RDBColumn](#).

Definition at line 347 of file `RDB.h`.

Referenced by `parseHeader()`, `setColumn()`, and `~RDB()`.

10.1.6.22 `string RDB::_line` [protected]

Line from [RDB](#) table.

Definition at line 350 of file `RDB.h`.

Referenced by `nRows()`, `parseLine()`, and `read()`.

The documentation for this class was generated from the following files:


- `RDB.h`
- `RDB.cc`

10.2 RDBColumn Class Reference

Provides interface for general column related methods.

```
#include <RDBColumn.h>
```

Inheritance diagram for `RDBColumn`:

**Public Types**

Enumerations for column definitions and error conditions.

- enum [Just](#) { **LEFT** = '<', **RIGHT** = '>' }
Acceptable column justifications.
- enum [Type](#) { **MONTH** = 'M', **NUMERIC** = 'N', **STRING** = 'S' }
Acceptable column types.

- enum [Err](#) {
NOERR = 0, **LOSTPRECISION** = EDOM, **NONNUMERIC** = EINVAL,
OUTOFRANGE = ERANGE,
NODATA = ENODATA }
Possible error conditions.
- enum [Status](#) { **CMOG** = 0x01, **CEOG** = 0x02, **CBOG** = 0x04 }
Acceptable column justifications.

Public Member Functions

Constructing, destructing, and initializing RDBColumn objects.

- [RDBColumn](#) (const string &name="", const string &def="") throw (RDBErr)
Assigns name and definition to [RDBColumn](#) object.
- [RDBColumn](#) (const [RDBColumn](#) &col)
Copies [RDBColumn](#) object.
- virtual [~RDBColumn](#) (void)
Deletes resources allocated by [RDBColumn](#) object.
- [RDBColumn](#) & operator= (const [RDBColumn](#) &col)
Copies [RDBColumn](#) object.
- virtual [RDBColumn](#) & operator= (const double &data)=0 throw (RDBErr)
Assigns data to [RDBColumn](#) object's `_data` member, converting as necessary.
- virtual [RDBColumn](#) & operator= (const long &data)=0 throw (RDBErr)
Assigns data to [RDBColumn](#) object's `_data` member, converting as necessary.
- virtual [RDBColumn](#) & operator= (const string &data)=0 throw (RDBErr)
Assigns data to [RDBColumn](#) object's `_data` member, converting as necessary.

Auto-indexing control methods.

- virtual void [advanceIdx](#) (void)=0
Increments index to the [RDBColumn](#)'s data elements.
- virtual void [rewind](#) (void)=0
Rewinds index to the [RDBColumn](#)'s data elements.

Group information ("break" column) methods.

- virtual void [setGroup](#) (bool group)
Turn on/off group tracking for this column object.
- bool [getGroup](#) (void) const
- virtual void [setGroupValue](#) (void)=0
Sets the group value to the current data value.
- virtual int [newGroup](#) (void)=0
Returns the group status of this column object.

Data member initializers.

- void [setName](#) (const string &name)
Sets the name.
- void [setDef](#) (const string &def) throw (RDBErr)
Sets the definition.
- void [setWidth](#) (const long width)
Sets the width.
- void [setType](#) (const RDBColumn::Type type)
Sets the type.
- void [setJust](#) (const RDBColumn::Just just)
Sets the justification.
- void [setDesc](#) (const string &desc)
Sets the description.
- void [setPrecision](#) (const int precision)
Sets the precision for numeric output and numeric to string conversion.
- void [setThrow](#) (const bool t=true)
Sets the exception throwing behavior.
- void [setErrNo](#) (const int no=0)
Sets the error status.
- virtual bool [setData](#) (const double &data)=0 throw (RDBErr)
Sets the data value, converting as necessary.
- virtual bool [setData](#) (const long &data)=0 throw (RDBErr)
Sets the data value, converting as necessary.

- virtual bool [setData](#) (const string &data)=0 throw (RDBErr)
Sets the data value, converting as necessary.

Methods to map RDBColumn's data to user-supplied memory.

- virtual void [mapData](#) (double data[], const size_t nelems=1) throw (RDBErr)
Maps data to user-supplied memory, if possible.
- virtual void [mapData](#) (long data[], const size_t nelems=1) throw (RDBErr)
Maps data to user-supplied memory, if possible.
- virtual void [mapData](#) (string data[], const size_t nelems=1) throw (RDBErr)
Maps data to user-supplied memory, if possible.

Data member accessors.

- string [getName](#) (void) const
Returns the name.
- string [getDef](#) (void)
Returns the definition.
- long [getWidth](#) (void) const
Returns the width.
- [RDBColumn::Type](#) [getType](#) (void) const
Returns the type.
- [RDBColumn::Just](#) [getJust](#) (void) const
Returns the justification.
- string [getDesc](#) (void) const
Returns the description.
- int [getPrecision](#) (void) const
Returns the precision.
- bool [getThrow](#) (void) const
Returns the state of the exception throwing behavior.
- char * [getErr](#) (void) const

Returns a brief description of the error condition.

- int `getErrNo` (void) const
Returns the error status.
- virtual void * `getData` (void)=0
Returns a pointer to the current data element.
- virtual bool `getData` (double &data)=0 throw (RDBErr)
Returns the value of the current data element, converting if necessary.
- virtual bool `getData` (long &data)=0 throw (RDBErr)
Returns the value of the current data element, converting if necessary.
- virtual bool `getData` (string &data)=0 throw (RDBErr)
Returns the value of the current data element, converting if necessary.
- virtual double `getDataDouble` (void)=0 throw (RDBErr)
Returns the value of the current data element, converting if necessary.
- virtual long `getDataLong` (void)=0 throw (RDBErr)
Returns the value of the current data element, converting if necessary.
- virtual string `getDataString` (void)=0 throw (RDBErr)
Returns the value of the current data element, converting if necessary.

Protected Member Functions

- void `convert` (const double &idata, double &odata) throw (RDBErr)
Used to converted data based on user requests.
- void `convert` (const double &idata, long &odata) throw (RDBErr)
Used to converted data based on user requests.
- void `convert` (const double &idata, string &odata) throw (RDBErr)
Used to converted data based on user requests.
- void `convert` (const long &idata, double &odata) throw (RDBErr)
Used to converted data based on user requests.
- void `convert` (const long &idata, long &odata) throw (RDBErr)
Used to converted data based on user requests.
- void `convert` (const long &idata, string &odata) throw (RDBErr)

Used to converted data based on user requests.

- void [convert](#) (const string &idata, double &odata) throw (RDBErr)
Used to converted data based on user requests.
- void [convert](#) (const string &idata, long &odata) throw (RDBErr)
Used to converted data based on user requests.
- void [convert](#) (const string &idata, string &odata) throw (RDBErr)
Used to converted data based on user requests.
- virtual istream & [read](#) (istream &is)=0 throw (RDBErr)
Called by the stream insertion operator.
- virtual istream & [extract](#) (istream &is, double &data) throw (RDBErr)
Overridden in the subclass of this datatype.
- virtual istream & [extract](#) (istream &is, long &data) throw (RDBErr)
Overridden in the subclass of this datatype.
- virtual istream & [extract](#) (istream &is, string &data) throw (RDBErr)
Overridden in the subclass of this datatype.
- virtual ostream & [write](#) (ostream &os) const =0
Called by the stream extraction operator.
- virtual ostream & [insert](#) (ostream &os, double &data) const
Overridden in the subclass of this datatype.
- virtual ostream & [insert](#) (ostream &os, long &data) const
Overridden in the subclass of this datatype.
- virtual ostream & [insert](#) (ostream &os, string &data) const
Overridden in the subclass of this datatype.

Protected Attributes

- string [_name](#)
Name.
- string [_def](#)

Definition.

- long [_width](#)
Width.
- [RDBColumn::Type _type](#)
Data type.
- [RDBColumn::Just _just](#)
Justification.
- string [_desc](#)
Description.
- bool [_changed](#)
Indicates state for the definition field.
- bool [_throw](#)
State of the exception throwing behavior.
- int [_errno](#)
Error state.
- int [_precision](#)
Precision used for stream output or numeric to string conversion.
- stringstream [_strstrm](#)
Used for numeric to string conversion.
- bool [_group](#)
This is a group column.
- bool [_initgroup](#)
Group been initialized.

Friends

Stream insertion and extraction operators.

- istream & [operator>>](#) (istream &is, [RDBColumn](#) &col) throw (RDBErr)
Read column from input stream.

- `istream & operator>> (istream &is, RDBColumn *col) throw (RDBErr)`
Read column from input stream.
- `ostream & operator<< (ostream &os, const RDBColumn &col)`
Write column to output stream.
- `ostream & operator<< (ostream &os, const RDBColumn *col)`
Write column to output stream.

10.2.1 Detailed Description

Provides interface for general column related methods.

Definition at line 43 of file RDBColumn.h.

10.2.2 Member Enumeration Documentation

10.2.2.1 enum RDBColumn::Just

Acceptable column justifications.

Definition at line 60 of file RDBColumn.h.

10.2.2.2 enum RDBColumn::Type

Acceptable column types.

Definition at line 62 of file RDBColumn.h.

10.2.2.3 enum RDBColumn::Err

Possible error conditions.

Definition at line 64 of file RDBColumn.h.

10.2.2.4 enum RDBColumn::Status

Acceptable column justifications.

Definition at line 65 of file RDBColumn.h.

10.2.3 Constructor & Destructor Documentation

10.2.3.1 RDBColumn::RDBColumn (const string & name = "", const string & def = "") throw (RDBErr)

Assigns name and definition to [RDBColumn](#) object.

Parameters:

name the column name.

def the column definition.

Initializes the [RDBColumn](#) name and definition. Sets the exception throwing behavior to true.

Definition at line 136 of file RDBColumn.cc.

10.2.3.2 RDBColumn::RDBColumn (const RDBColumn & col)

Copies [RDBColumn](#) object.

Parameters:

col the [RDBColumn](#) object to copy.

Copies the argument.

Definition at line 165 of file RDBColumn.cc.

10.2.3.3 RDBColumn::~~RDBColumn (void) [virtual]

Deletes resources allocated by [RDBColumn](#) object.

Nothing to do.

Definition at line 180 of file RDBColumn.cc.

10.2.4 Member Function Documentation

10.2.4.1 RDBColumn & RDBColumn::operator= (const RDBColumn & col)

Copies [RDBColumn](#) object.

Parameters:

col the [RDBColumn](#) object to copy.

Definition at line 191 of file RDBColumn.cc.

References `_changed`, `_def`, `_desc`, `_errno`, `_group`, `_just`, `_name`, `_precision`, `_throw`, `_type`, and `_width`.

Referenced by `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::operator=()`.

10.2.4.2 virtual RDBColumn& RDBColumn::operator= (const double & data)
throw (RDBErr) [pure virtual]

Assigns data to [RDBColumn](#) object's `_data` member, converting as necessary.

Implemented in [RDBColumnTmpl< long, string, double >](#).

10.2.4.3 virtual RDBColumn& RDBColumn::operator= (const long & data)
throw (RDBErr) [pure virtual]

Assigns data to [RDBColumn](#) object's `_data` member, converting as necessary.

Implemented in [RDBColumnTmpl< long, string, double >](#).

10.2.4.4 virtual RDBColumn& RDBColumn::operator= (const string & data)
throw (RDBErr) [pure virtual]

Assigns data to [RDBColumn](#) object's `_data` member, converting as necessary.

Implemented in [RDBColumnTmpl< long, string, double >](#).

10.2.4.5 virtual void RDBColumn::advanceIdx (void) [pure virtual]

Increments index to the [RDBColumn](#)'s data elements.

Implemented in [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >](#), and [RDBColumnTmpl< long, string, double >](#).

Referenced by [RDB::advanceIdx\(\)](#), and [RDB::read\(\)](#).

10.2.4.6 virtual void RDBColumn::rewind (void) [pure virtual]

Rewinds index to the [RDBColumn](#)'s data elements.

Implemented in [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >](#), and [RDBColumnTmpl< long, string, double >](#).

Referenced by [RDB::rewind\(\)](#).

10.2.4.7 void RDBColumn::setGroup (bool group) [virtual]

Turn on/off group tracking for this column object.

Parameters:

group indicates whether or not this is a group column.

Reimplemented in [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >](#), and [RDBColumnTmpl< long, string, double >](#).

Definition at line 219 of file RDBColumn.cc.

References `_group`.

Referenced by `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::setGroup()`, and `RDB::setGroup()`.

10.2.4.8 `bool RDBColumn::getGroup (void) const`

Returns group status, RBOG if at beginning of a group, REOG if at end of a group, or REOL if in the middle of a group.

Returns:

Whether or not this is a group column.

Definition at line 232 of file RDBColumn.cc.

References `_group`.

Referenced by `RDB::getGroup()`.

10.2.4.9 `virtual void RDBColumn::setGroupValue (void)` [pure virtual]

Sets the group value to the current data value.

Implemented in `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >`, and `RDBColumnTmpl< long, string, double >`.

10.2.4.10 `virtual int RDBColumn::newGroup (void)` [pure virtual]

Returns the group status of this column object.

Implemented in `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >`, and `RDBColumnTmpl< long, string, double >`.

Referenced by `RDB::read()`.

10.2.4.11 `void RDBColumn::setName (const string & name)`

Sets the name.

Parameters:

name the `RDBColumn` name to use.

Sets the `RDBColumn` name.

Definition at line 247 of file RDBColumn.cc.

References `_name`.

Referenced by `RDB::setColumn()`, and `RDB::setName()`.

10.2.4.12 void RDBColumn::setDef (const string & *def*) throw (RDBErr)

Sets the definition.

Parameters:

def the [RDBColumn](#) definition to use.

Exceptions:

RDBErrColFmt error if the definition is an unrecognized format.

Sets the [RDBColumn](#) definition, as well as the width, type, justification, and description.

Definition at line 266 of file `RDBColumn.cc`.

References `_changed`, `_def`, `_desc`, `_just`, `_name`, `_type`, and `_width`.

Referenced by `RDB::setColumn()`, and `RDB::setDef()`.

10.2.4.13 void RDBColumn::setWidth (const long *width*)

Sets the width.

Parameters:

width the width of the [RDBColumn](#).

The width has no effect on the storage or printing of the data. The [RDB](#) docs indicate that it is used only by the `ptbl` command.

Definition at line 340 of file `RDBColumn.cc`.

References `_changed`, and `_width`.

Referenced by `RDB::setWidth()`.

10.2.4.14 void RDBColumn::setType (const RDBColumn::Type *type*)

Sets the type.

Parameters:

type of the [RDBColumn](#).

Possible values are 'M' for month, 'N' for numeric, 'S' for string. String is the default type.

Definition at line 357 of file RDBColumn.cc.

References `_changed`, and `_type`.

Referenced by `RDB::setType()`.

10.2.4.15 void RDBColumn::setJust (const RDBColumn::Just *just*)

Sets the justification.

Parameters:

just the justification of the data when printing.

Possible values are '<' for left justification and '>' for right justification. Default is for months and strings to be left justified and numeric data to be right justified.

Definition at line 375 of file RDBColumn.cc.

References `_changed`, and `_just`.

Referenced by `RDB::setJust()`.

10.2.4.16 void RDBColumn::setDesc (const string & *desc*)

Sets the description.

Parameters:

desc is the column documentation.

Sets the [RDBColumn](#) description.

Definition at line 391 of file RDBColumn.cc.

References `_changed`, and `_desc`.

Referenced by `RDB::setDesc()`.

10.2.4.17 void RDBColumn::setPrecision (const int *precision*)

Sets the precision for numeric output and numeric to string conversion.

Parameters:

precision Sets the [RDBColumn](#) precision which controls the output precision of floating point data.

Definition at line 408 of file RDBColumn.cc.

References `_precision`.

10.2.4.18 void RDBColumn::setThrow (const bool *t* = true)

Sets the exception throwing behavior.

Parameters:

t state of the exception throwing behavior.

Sets the [RDBColumn](#) exception throwing behavior.

Definition at line 423 of file RDBColumn.cc.

References `_throw`.

10.2.4.19 void RDBColumn::setErrNo (const int *no* = 0)

Sets the error status.

Parameters:

no Sets the [RDBColumn](#) error status.

Definition at line 438 of file RDBColumn.cc.

References `_errno`.

10.2.4.20 virtual bool RDBColumn::setData (const double & *data*) throw (RDBErr) [pure virtual]

Sets the data value, converting as necessary.

Implemented in [RDBColumnTmpl< long, string, double >](#).

Referenced by `RDB::parseLine()`, `RDB::read()`, and `RDB::setData()`.

10.2.4.21 virtual bool RDBColumn::setData (const long & *data*) throw (RDBErr) [pure virtual]

Sets the data value, converting as necessary.

Implemented in [RDBColumnTmpl< long, string, double >](#).

10.2.4.22 virtual bool RDBColumn::setData (const string & *data*) throw (RDBErr) [pure virtual]

Sets the data value, converting as necessary.

Implemented in [RDBColumnTpl< long, string, double >](#).

10.2.4.23 void RDBColumn::mapData (double *data*[], const size_t *nelems* = 1) throw (RDBErr) [virtual]

Maps data to user-supplied memory, if possible.

Definition at line 448 of file RDBColumn.cc.

References `_name`.

Referenced by `RDB::mapData()`.

10.2.4.24 void RDBColumn::mapData (long *data*[], const size_t *nelems* = 1) throw (RDBErr) [virtual]

Maps data to user-supplied memory, if possible.

Reimplemented in [RDBColumnTpl< long, string, double >](#).

Definition at line 459 of file RDBColumn.cc.

References `_name`.

10.2.4.25 void RDBColumn::mapData (string *data*[], const size_t *nelems* = 1) throw (RDBErr) [virtual]

Maps data to user-supplied memory, if possible.

Definition at line 470 of file RDBColumn.cc.

References `_name`.

10.2.4.26 string RDBColumn::getName (void) const

Returns the name.

Returns the [RDBColumn](#) name.

Definition at line 484 of file RDBColumn.cc.

References `_name`.

Referenced by `RDB::close()`, `RDB::getName()`, and `RDB::write()`.

10.2.4.27 string RDBColumn::getDef (void)

Returns the definition.

Returns the [RDBColumn](#) definition, reconstructing it from its constituent parts if any of them have changed.

Definition at line 498 of file RDBColumn.cc.

References `_changed`, `_def`, `_just`, `_strstm`, `_type`, and `_width`.

Referenced by `RDB::close()`, `RDB::getDef()`, and `RDB::write()`.

10.2.4.28 `long RDBColumn::getWidth (void) const`

Returns the width.

Returns the [RDBColumn](#) width.

Definition at line 540 of file RDBColumn.cc.

Referenced by `RDB::getWidth()`.

10.2.4.29 `RDBColumn::Type RDBColumn::getType (void) const`

Returns the type.

Returns the [RDBColumn](#) type.

Definition at line 553 of file RDBColumn.cc.

Referenced by `RDB::getType()`.

10.2.4.30 `RDBColumn::Just RDBColumn::getJust (void) const`

Returns the justification.

Returns the [RDBColumn](#) justification.

Definition at line 566 of file RDBColumn.cc.

Referenced by `RDB::getJust()`.

10.2.4.31 `string RDBColumn::getDesc (void) const`

Returns the description.

Returns the [RDBColumn](#) description.

Definition at line 579 of file RDBColumn.cc.

Referenced by `RDB::getDesc()`.

10.2.4.32 `int RDBColumn::getPrecision (void) const`

Returns the precision.

Returns the [RDBColumn](#) precision used for stream output.

Definition at line 592 of file RDBColumn.cc.

10.2.4.33 **bool RDBColumn::getThrow (void) const**

Returns the state of the exception throwing behavior.

Returns the [RDBColumn](#) exception throwing flag.

Definition at line 605 of file RDBColumn.cc.

10.2.4.34 **char * RDBColumn::getErr (void) const**

Returns a brief description of the error condition.

Returns a string describing the [RDBColumn](#) error flag.

Definition at line 618 of file RDBColumn.cc.

10.2.4.35 **int RDBColumn::getErrNo (void) const**

Returns the error status.

Returns the [RDBColumn](#) error flag.

Definition at line 631 of file RDBColumn.cc.

10.2.4.36 **virtual void* RDBColumn::getData (void) [pure virtual]**

Returns a pointer to the current data element.

Implemented in [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >](#), and [RDBColumnTmpl< long, string, double >](#).

10.2.4.37 **virtual bool RDBColumn::getData (double & data) throw (RDBErr) [pure virtual]**

Returns the value of the current data element, converting if necessary.

Implemented in [RDBColumnTmpl< long, string, double >](#).

10.2.4.38 **virtual bool RDBColumn::getData (long & data) throw (RDBErr) [pure virtual]**

Returns the value of the current data element, converting if necessary.

Implemented in [RDBColumnTmpl< long, string, double >](#).

10.2.4.39 `virtual bool RDBColumn::getData (string & data) throw (RDBErr)`
[pure virtual]

Returns the value of the current data element, converting if necessary.

Implemented in [RDBColumnTmpl< long, string, double >](#).

10.2.4.40 `virtual double RDBColumn::getDataDouble (void) throw (RDBErr)`
[pure virtual]

Returns the value of the current data element, converting if necessary.

Implemented in [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >](#), and [RDBColumnTmpl< long, string, double >](#).

Referenced by [RDB::getData\(\)](#), and [RDB::getDataDouble\(\)](#).

10.2.4.41 `virtual long RDBColumn::getDataLong (void) throw (RDBErr)`
[pure virtual]

Returns the value of the current data element, converting if necessary.

Implemented in [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >](#), and [RDBColumnTmpl< long, string, double >](#).

Referenced by [RDB::getData\(\)](#), and [RDB::getDataLong\(\)](#).

10.2.4.42 `virtual string RDBColumn::getDataString (void) throw (RDBErr)`
[pure virtual]

Returns the value of the current data element, converting if necessary.

Implemented in [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >](#), and [RDBColumnTmpl< long, string, double >](#).

Referenced by [RDB::getData\(\)](#), and [RDB::getDataString\(\)](#).

10.2.4.43 `void RDBColumn::convert (const double & idata, double & odata)`
`throw (RDBErr)` [protected]

Used to converted data based on user requests.

Parameters:

idata input data.

odata output data.

Handles the trivial conversion for double to double for child classes.

Definition at line 647 of file [RDBColumn.cc](#).

Referenced by RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getData(),
 RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getDataDouble(),
 RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getDataLong(),
 RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getDataString(),
 RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::operator=(), and
 RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::setData().

10.2.4.44 void RDBColumn::convert (const double & *idata*, long & *odata*) throw (RDBErr) [protected]

Used to converted data based on user requests.

Parameters:

idata input data.
odata output data.

Handles the trivial conversion for double to long for child classes.

Definition at line 664 of file RDBColumn.cc.

10.2.4.45 void RDBColumn::convert (const double & *idata*, string & *odata*) throw (RDBErr) [protected]

Used to converted data based on user requests.

Parameters:

idata input data.
odata output data.

Handles the non-trivial conversion for double to string for child classes.

Warning:

This is slow. Like dirt. Don't do it often.

Definition at line 684 of file RDBColumn.cc.

10.2.4.46 void RDBColumn::convert (const long & *idata*, double & *odata*) throw (RDBErr) [protected]

Used to converted data based on user requests.

Parameters:

idata input data.

odata output data.

Handles the trivial conversion for long to double for child classes.

Definition at line 705 of file RDBColumn.cc.

10.2.4.47 void RDBColumn::convert (const long & *idata*, long & *odata*) throw (RDBErr) [protected]

Used to converted data based on user requests.

Parameters:

idata input data.

odata output data.

Handles the trivial conversion for long to long for child classes.

Definition at line 722 of file RDBColumn.cc.

10.2.4.48 void RDBColumn::convert (const long & *idata*, string & *odata*) throw (RDBErr) [protected]

Used to converted data based on user requests.

Parameters:

idata input data.

odata output data.

Handles the non-trivial conversion for long to string for child classes.

Warning:

This is slow. Like dirt. Don't do it often.

Definition at line 741 of file RDBColumn.cc.

10.2.4.49 void RDBColumn::convert (const string & *idata*, double & *odata*) throw (RDBErr) [protected]

Used to converted data based on user requests.

Parameters:

idata input data.

odata output data.

Exceptions:

RDBErr error if idata is non-numeric.

Handles the non-trivial conversion for string to double for child classes.

Definition at line 764 of file RDBColumn.cc.

10.2.4.50 void RDBColumn::convert (const string & idata, long & odata) throw (RDBErr) [protected]

Used to converted data based on user requests.

Parameters:

idata input data.

odata output data.

Exceptions:

RDBErr error if idata is non-numeric.

RDBErr error if idata represents a floating point number and precision is lost converting to integer number.

Handles the non-trivial conversion for string to long for child classes.

Definition at line 796 of file RDBColumn.cc.

10.2.4.51 void RDBColumn::convert (const string & idata, string & odata) throw (RDBErr) [protected]

Used to converted data based on user requests.

Parameters:

idata input data.

odata output data.

Handles the trivial conversion for string to string for child classes.

Definition at line 848 of file RDBColumn.cc.

10.2.4.52 virtual istream& RDBColumn::read (istream & *is*) throw (RDBErr)
[protected, pure virtual]

Called by the stream insertion operator.

Implemented in [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >](#), and [RDBColumnTmpl< long, string, double >](#).

10.2.4.53 istream & RDBColumn::extract (istream & *is*, double & *data*) throw (RDBErr)
[protected, virtual]

Overridden in the subclass of this datatype.

Parameters:

is input string.

data double data.

Returns:

istream the input stream.

Extracts a double from the input stream.

Definition at line 867 of file RDBColumn.cc.

Referenced by [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::read\(\)](#).

10.2.4.54 istream & RDBColumn::extract (istream & *is*, long & *data*) throw (RDBErr)
[protected, virtual]

Overridden in the subclass of this datatype.

Parameters:

is input string.

data long data.

Returns:

istream the input stream.

Extracts a long from the input stream.

Definition at line 891 of file RDBColumn.cc.

10.2.4.55 `istream & RDBColumn::extract (istream & is, string & data) throw (RDBErr)` `[protected, virtual]`

Overridden in the subclass of this datatype.

Parameters:

is input string.
data string data.

Returns:

istream the input stream.

Extracts a string from the input stream. Extraction stops at the first tab or newline character.

Definition at line 917 of file RDBColumn.cc.

10.2.4.56 `virtual ostream& RDBColumn::write (ostream & os) const` `[protected, pure virtual]`

Called by the stream extraction operator.

Implemented in [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >](#), and [RDBColumnTmpl< long, string, double >](#).

10.2.4.57 `ostream & RDBColumn::insert (ostream & os, double & data) const` `[protected, virtual]`

Overridden in the subclass of this datatype.

Parameters:

os output string.
data double data.

Returns:

ostream the output stream.

Inserts a double into the output stream.

Definition at line 953 of file RDBColumn.cc.

Referenced by [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::write\(\)](#).

10.2.4.58 ostream & RDBColumn::insert (ostream & *os*, long & *data*) const
[protected, virtual]

Overridden in the subclass of this datatype.

Parameters:

os output string.
data double data.

Returns:

ostream the output stream.

Inserts a long into the output stream.

Definition at line 972 of file RDBColumn.cc.

10.2.4.59 ostream & RDBColumn::insert (ostream & *os*, string & *data*) const
[protected, virtual]

Overridden in the subclass of this datatype.

Parameters:

os output string.
data double data.

Returns:

ostream the output stream.

Inserts a string into the output stream.

Definition at line 991 of file RDBColumn.cc.

10.2.5 Friends And Related Function Documentation**10.2.5.1 istream& operator>> (istream & *is*, RDBColumn & *col*) throw (RDBErr)** [friend]

Read column from input stream.

Parameters:

is input stream.
col [RDBColumn](#) to fill.

Returns:

A reference to the input stream.

Reads one data element into this object.

Definition at line 38 of file RDBColumn.cc.

10.2.5.2 istream& operator>> (istream & *is*, RDBColumn * *col*) throw (RDBErr) [friend]

Read column from input stream.

Parameters:

is input stream.

col [RDBColumn](#) to fill.

Returns:

A reference to the input stream.

Reads one data element into this object.

Definition at line 69 of file RDBColumn.cc.

10.2.5.3 ostream& operator<< (ostream & *os*, const RDBColumn & *col*) [friend]

Write column to output stream.

Parameters:

os output stream.

col [RDBColumn](#) to fill.

Returns:

A reference to the output stream.

Writes one data element from this object.

Definition at line 100 of file RDBColumn.cc.

10.2.5.4 ostream& operator<< (ostream & *os*, const RDBColumn * *col*) [friend]

Write column to output stream.

Parameters:

os output stream.
col [RDBColumn](#) to fill.

Returns:

A reference to the output stream.

Writes one data element from this object.

Definition at line 119 of file RDBColumn.cc.

10.2.6 Member Data Documentation**10.2.6.1 string RDBColumn::_name** [protected]

Name.

Definition at line 225 of file RDBColumn.h.

Referenced by getName(), mapData(), operator=(), setDef(), and setName().

10.2.6.2 string RDBColumn::_def [protected]

Definition.

Definition at line 227 of file RDBColumn.h.

Referenced by getDef(), operator=(), and setDef().

10.2.6.3 long RDBColumn::_width [protected]

Width.

Definition at line 229 of file RDBColumn.h.

Referenced by getDef(), operator=(), setDef(), and setWidth().

10.2.6.4 RDBColumn::Type RDBColumn::_type [protected]

Data type.

Definition at line 231 of file RDBColumn.h.

Referenced by getDef(), operator=(), setDef(), and setType().

10.2.6.5 RDBColumn::Just RDBColumn::_just [protected]

Justification.

Definition at line 233 of file RDBColumn.h.

Referenced by `getDef()`, `operator=()`, `setDef()`, and `setJust()`.

10.2.6.6 `string RDBColumn::_desc` [protected]

Description.

Definition at line 235 of file RDBColumn.h.

Referenced by `operator=()`, `setDef()`, and `setDesc()`.

10.2.6.7 `bool RDBColumn::_changed` [protected]

Indicates state for the definition field.

Definition at line 237 of file RDBColumn.h.

Referenced by `getDef()`, `operator=()`, `setDef()`, `setDesc()`, `setJust()`, `setType()`, and `setWidth()`.

10.2.6.8 `bool RDBColumn::_throw` [protected]

State of the exception throwing behavior.

Definition at line 240 of file RDBColumn.h.

Referenced by `operator=()`, and `setThrow()`.

10.2.6.9 `int RDBColumn::_errno` [protected]

Error state.

Definition at line 242 of file RDBColumn.h.

Referenced by `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getData()`, `operator=()`, `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::setData()`, and `setErrNo()`.

10.2.6.10 `int RDBColumn::_precision` [protected]

Precision used for stream output or numeric to string conversion.

Definition at line 244 of file RDBColumn.h.

Referenced by `operator=()`, and `setPrecision()`.

10.2.6.11 `stringstream RDBColumn::_strstm` [protected]

Used for numeric to string conversion.

Definition at line 246 of file RDBColumn.h.

Referenced by `getDef()`.

10.2.6.12 bool RDBColumn::_group [protected]

This is a group column.

Definition at line 248 of file `RDBColumn.h`.

Referenced by `getGroup()`, `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::mapData()`, `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::newGroup()`, `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::operator=()`, `operator=()`, `setGroup()`, and `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::setGroupValue()`.

10.2.6.13 bool RDBColumn::_initgroup [protected]

Group been initialized.

Definition at line 250 of file `RDBColumn.h`.

Referenced by `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::newGroup()`.

The documentation for this class was generated from the following files:


- `RDBColumn.h`
- `RDBColumn.cc`

10.3 RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 > Class Template Reference


Parameterizes [RDBColumn](#) interface for many data types.

`#include <RDBColumnTmpl.h>`

Inheritance diagram for `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >`:



Collaboration diagram for RDBColumnTplt< Tmpl0, Tmpl1, Tmpl2 >:



Public Member Functions

Constructing, destructing, and initializing RDB columns.

- [RDBColumnTplt](#) (const string &name="", const string &def="") throw (RDBErr)
Assigns name and definition.
- [RDBColumnTplt](#) (const [RDBColumnTplt](#)< Tmpl0, Tmpl1, Tmpl2 > &rdbcolumnntmpl)
Copies [RDBColumnTplt](#) object.
- [~RDBColumnTplt](#) (void)
Deletes resources allocated by [RDBColumnTplt](#) object.
- [RDBColumn](#) & [operator=](#) (const [RDBColumnTplt](#)< Tmpl0, Tmpl1, Tmpl2 > &rdbcolumnntmpl)
Copies [RDBColumnTplt](#) object.
- virtual [RDBColumn](#) & [operator=](#) (const Tmpl0 &data) throw (RDBErr)
Assigns data to [RDBColumn](#) object's `_data` member, converting as necessary.
- virtual [RDBColumn](#) & [operator=](#) (const Tmpl1 &data) throw (RDBErr)
Assigns data to [RDBColumn](#) object's `_data` member, converting as necessary.
- virtual [RDBColumn](#) & [operator=](#) (const Tmpl2 &data) throw (RDBErr)
Assigns data to [RDBColumn](#) object's `_data` member, converting as necessary.

Auto-indexing control methods.

- virtual void [advanceIdx](#) (void)
Increments index to the [RDBColumn](#)'s data elements.
- virtual void [rewind](#) (void)
Rewinds index to the [RDBColumn](#)'s data elements.

Group information ("break" column) methods.

- virtual void [setGroup](#) (bool group)
• virtual void [setGroupValue](#) (void)
Sets the group value to the current data value.
- virtual int [newGroup](#) (void)
Returns the group status of this column object.

Data member initializers.

- virtual bool [setData](#) (const Tmpl0 &data) throw (RDBErr)
Sets the data value, converting as necessary.
- virtual bool [setData](#) (const Tmpl1 &data) throw (RDBErr)
Sets the data value, converting as necessary.
- virtual bool [setData](#) (const Tmpl2 &data) throw (RDBErr)
Sets the data value, converting as necessary.

Methods to map RDBColumn's data to user-supplied memory.

- virtual void [mapData](#) (Tmpl0 data[], const size_t nelems) throw (RDBErr)
Maps data to user-supplied memory.

Data member accessors.

- void * [getData](#) (void)
Returns a pointer to the current data element.
- virtual bool [getData](#) (Tmpl0 &data) throw (RDBErr)
Returns the value of the current data element, converting if necessary.
- virtual bool [getData](#) (Tmpl1 &data) throw (RDBErr)
Returns the value of the current data element, converting if necessary.
- virtual bool [getData](#) (Tmpl2 &data) throw (RDBErr)
Returns the value of the current data element, converting if necessary.
- virtual double [getDataDouble](#) (void) throw (RDBErr)
Returns the value of the current data element, converting if necessary.
- virtual long [getDataLong](#) (void) throw (RDBErr)

Returns the value of the current data element, converting if necessary.

- virtual string [getDataString](#) (void) throw (RDBErr)
Returns the value of the current data element, converting if necessary.

Protected Member Functions

- virtual istream & [read](#) (istream &is) throw (RDBErr)
Called by the stream insertion operator.
- virtual ostream & [write](#) (ostream &os) const
Called by the stream extraction operator.
- void [cleanup](#) (void)
Deletes resources allocated by [RDBColumnTplt](#) object.

Protected Attributes

- Tmpl0 * [_data](#)
Pointer to the data managed by object.
- size_t [_idx](#)
Index into the data.
- size_t [_nelems](#)
Number of elements of data.
- bool [_mine](#)
Indicates that [RDBColumnTplt](#) is responsible for deallocating the data.
- Tmpl0 [_groupvalue](#)
Current group value.

10.3.1 Detailed Description

template<class Tmpl0, class Tmpl1, class Tmpl2> class RDBColumnTplt< Tmpl0, Tmpl1, Tmpl2 >

Parameterizes [RDBColumn](#) interface for many data types.

Definition at line 38 of file RDBColumnTplt.h.

10.3.2 Constructor & Destructor Documentation

10.3.2.1 `template<class Tmpl0, class Tmpl1, class Tmpl2>
RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::RDBColumnTmpl (const
string & name = "", const string & def = "") throw (RDBErr) [inline]`

Assigns name and definition.

Parameters:

name the column name.

def the column definition.

Allocates space for a single data element of type Tmpl1.

Definition at line 37 of file RDBColumnTmpl.cc.

10.3.2.2 `template<class Tmpl0, class Tmpl1, class Tmpl2>
RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::RDBColumnTmpl (const
RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 > & rdbcolumntmpl) [inline]`

Copies [RDBColumnTmpl](#) object.

Parameters:

rdbcolumntmpl col the [RDBColumn](#) object to copy.

Makes a shallow copy of the argument. The two [RDBColumn](#) objects share data elements.

Definition at line 58 of file RDBColumnTmpl.cc.

References `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data`,
`RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx`, `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_mine`, and `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_nelems`.

10.3.2.3 `template<class Tmpl0, class Tmpl1, class Tmpl2>
RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::~~RDBColumnTmpl (void)
[inline]`

Deletes resources allocated by [RDBColumnTmpl](#) object.

Responsible for freeing data element memory allocated by the [RDBColumn](#) object.

Definition at line 76 of file RDBColumnTmpl.cc.

References `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::cleanup()`.

10.3.3 Member Function Documentation

10.3.3.1 `template<class Tmpl0, class Tmpl1, class Tmpl2> RDBColumn & RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::operator= (const RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 > & col) [inline]`

Copies [RDBColumnTmpl](#) object.

Parameters:

col the [RDBColumn](#) object to copy.

Makes a shallow copy of the argument. The two [RDBColumn](#) objects share data elements.

Definition at line 93 of file [RDBColumnTmpl.cc](#).

References [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data](#), [RDBColumn::_group](#), [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx](#), [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_mine](#), [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_nelems](#), [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::cleanup\(\)](#), and [RDBColumn::operator=\(\)](#).

10.3.3.2 `template<class Tmpl0, class Tmpl1, class Tmpl2> RDBColumn & RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::operator= (const Tmpl0 & data) throw (RDBErr) [inline, virtual]`

Assigns data to [RDBColumn](#) object's `_data` member, converting as necessary.

Parameters:

data Assigns the value to the current [RDBColumn](#) data element.

Definition at line 124 of file [RDBColumnTmpl.cc](#).

References [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data](#), [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx](#), and [RDBColumn::convert\(\)](#).

10.3.3.3 `template<class Tmpl0, class Tmpl1, class Tmpl2> RDBColumn & RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::operator= (const Tmpl1 & data) throw (RDBErr) [inline, virtual]`

Assigns data to [RDBColumn](#) object's `_data` member, converting as necessary.

Parameters:

data

Exceptions:

RDBErr error if the user attempts to convert non-numeric string data to a numeric column.

RDBErr error if the user attempts to convert string data representing a floating point number to an integer column.

Assigns the value to the current [RDBColumn](#) data element.

Definition at line 155 of file RDBColumnTmpl.cc.

References [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data](#), [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx](#), and [RDBColumn::convert\(\)](#).

10.3.3.4 `template<class Tmpl0, class Tmpl1, class Tmpl2> RDBColumn & RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::operator= (const Tmpl2 & data) throw (RDBErr)` [inline, virtual]

Assigns data to [RDBColumn](#) object's `_data` member, converting as necessary.

Parameters:

data

Exceptions:

RDBErr error if the user attempts to convert non-numeric string data to a numeric column.

RDBErr error if the user attempts to convert string data representing a floating point number to an integer column.

Assigns the value to the current [RDBColumn](#) data element.

Definition at line 186 of file RDBColumnTmpl.cc.

References [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data](#), [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx](#), and [RDBColumn::convert\(\)](#).

10.3.3.5 `template<class Tmpl0, class Tmpl1, class Tmpl2> void RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::advanceIdx (void)` [inline, virtual]

Increments index to the [RDBColumn](#)'s data elements.

Advances the automatic index for the data elements by one.

Implements [RDBColumn](#).

Definition at line 212 of file RDBColumnTmpl.cc.

References RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx, and RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_nelems.

Referenced by RDB::advanceIdx().

10.3.3.6 template<class Tmpl0, class Tmpl1, class Tmpl2> void RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::rewind (void) [inline, virtual]

Rewinds index to the RDBColumn's data elements.

Rewinds the automatic index for the data elements to the first element.

Implements [RDBColumn](#).

Definition at line 228 of file RDBColumnTmpl.cc.

References RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx.

10.3.3.7 template<class Tmpl0, class Tmpl1, class Tmpl2> void RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::setGroup (bool group) [inline, virtual]

Parameters:

group indicates whether or not this is a group column.

Reimplemented from [RDBColumn](#).

Definition at line 242 of file RDBColumnTmpl.cc.

References RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data, RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx, RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_mine, RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_nelems, and RDBColumn::setGroup().

Referenced by RDB::setGroup().

10.3.3.8 template<class Tmpl0, class Tmpl1, class Tmpl2> void RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::setGroupValue (void) [inline, virtual]

Sets the group value to the current data value.

Sets the group for this object to the current data element.

Implements [RDBColumn](#).

Definition at line 268 of file RDBColumnTmpl.cc.

References RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data, RDBColumn::_group, RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_groupvalue,

RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx, and RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_nelems.

10.3.3.9 `template<class Tmpl0, class Tmpl1, class Tmpl2> int
RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::newGroup (void) [inline,
virtual]`

Returns the group status of this column object.

Returns:

True if the data element is in a new group.

Implements [RDBColumn](#).

Definition at line 285 of file RDBColumnTmpl.cc.

References RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data, RDBColumn::_group, RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_groupvalue, RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx, RDBColumn::_initgroup, and RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_nelems.

10.3.3.10 `template<class Tmpl0, class Tmpl1, class Tmpl2> bool
RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::setData (const Tmpl0 &
data) throw (RDBErr) [inline, virtual]`

Sets the data value, converting as necessary.

Parameters:

data

Returns:

True upon successful conversion, false otherwise.

Assigns the value to the current [RDBColumn](#) data element.

Definition at line 343 of file RDBColumnTmpl.cc.

References RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data, RDBColumn::_errno, RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx, and RDBColumn::convert().

Referenced by RDB::setData().

10.3.3.11 `template<class Tmpl0, class Tmpl1, class Tmpl2> bool
RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::setData (const Tmpl1 &
data) throw (RDBErr) [inline, virtual]`

Sets the data value, converting as necessary.

Parameters:

data

Exceptions:

RDBErr error if the user attempts to convert non-numeric string data to a numeric column.

RDBErr error if the user attempts to convert string data representing a floating point number to an integer column.

Returns:

True upon successful conversion, false otherwise.

Assigns the value to the current [RDBColumn](#) data element.

Definition at line 376 of file RDBColumnTmpl.cc.

References [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data](#), [RDBColumn::_errno](#), [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx](#), and [RDBColumn::convert\(\)](#).

10.3.3.12 `template<class Tmpl0, class Tmpl1, class Tmpl2> bool
RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::setData (const Tmpl2 &
data) throw (RDBErr) [inline, virtual]`

Sets the data value, converting as necessary.

Parameters:

data

Exceptions:

RDBErr error if the user attempts to convert non-numeric string data to a numeric column.

RDBErr error if the user attempts to convert string data representing a floating point number to an integer column.

Returns:

True upon successful conversion, false otherwise.

Assigns the value to the current [RDBColumn](#) data element.

Definition at line 409 of file RDBColumnTmpl.cc.

References RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data, RDBColumn::_errno, RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx, and RDBColumn::convert().

10.3.3.13 `template<class Tmpl0, class Tmpl1, class Tmpl2> void RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::mapData (Tmpl0 data[], const size_t nelems) throw (RDBErr) [inline, virtual]`

Maps data to user-supplied memory.

Parameters:

data pointer to a data element of type Tmpl0.

nelems number of data elements in the array pointed by data.

This method associates user allocated memory pointed to by data with this [RDBColumn](#) object. The user is responsible for freeing the memory pointed to by data after the [RDBColumn](#) is destroyed.

Definition at line 440 of file RDBColumnTmpl.cc.

References RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data, RDBColumn::_group, RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx, RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_mine, RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_nelems, and RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::cleanup().

Referenced by RDB::mapData().

10.3.3.14 `template<class Tmpl0, class Tmpl1, class Tmpl2> void * RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getData (void) [inline, virtual]`

Returns a pointer to the current data element.

Returns:

Pointer to the current data element.

This method returns a pointer to the current data element. Modifications to the data returned are evident within this object.

Implements [RDBColumn](#).

Definition at line 466 of file RDBColumnTmpl.cc.

References RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data, and RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx.

10.3.3.15 `template<class Tmpl0, class Tmpl1, class Tmpl2> bool
RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getData (Tmpl0 & data)
throw (RDBErr) [inline, virtual]`

Returns the value of the current data element, converting if necessary.

Parameters:

data assigned the value of the current data element in this object.

Returns:

True if the conversion was successful, false otherwise.

Assigns the value of the current [RDBColumn](#) data element to the argument.

Definition at line 484 of file RDBColumnTmpl.cc.

References RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data, RDBColumn::_
errno, RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx, and RDBCol-
umn::convert().

10.3.3.16 `template<class Tmpl0, class Tmpl1, class Tmpl2> bool
RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getData (Tmpl1 & data)
throw (RDBErr) [inline, virtual]`

Returns the value of the current data element, converting if necessary.

Parameters:

data assigned the value of the current data element in this object.

Exceptions:

[RDBErr](#) error if the user attempts to convert a string column with non-numeric
data to a numeric argument.

[RDBErr](#) error if the user attempts to convert a string column representing a float-
ing point number to an integer argument.

Returns:

True if the conversion was successful, false otherwise.

Assigns the value of the current [RDBColumn](#) data element to the argument.

Definition at line 517 of file RDBColumnTmpl.cc.

References RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data, RDBColumn::_
errno, RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx, and RDBCol-
umn::convert().

10.3.3.17 `template<class Tmpl0, class Tmpl1, class Tmpl2> bool
RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getData (Tmpl2 & data)
throw (RDBErr) [inline, virtual]`

Returns the value of the current data element, converting if necessary.

Parameters:

data assigned the value of the current data element in this object.

Exceptions:

RDBErr error if the user attempts to convert a string column with non-numeric data to a numeric argument.

RDBErr error if the user attempts to convert a string column representing a floating point number to an integer argument.

Returns:

True if the conversion was successful, false otherwise.

Assigns the value of the current [RDBColumn](#) data element to the argument.

Definition at line 550 of file `RDBColumnTmpl.cc`.

References `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data`, `RDBColumn::_errno`, `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx`, and `RDBColumn::convert()`.

10.3.3.18 `template<class Tmpl0, class Tmpl1, class Tmpl2> double
RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getDataDouble (void) throw (
RDBErr) [inline, virtual]`

Returns the value of the current data element, converting if necessary.

Exceptions:

RDBErr error if the user attempts to convert a string column with non-numeric data to a numeric argument.

Returns:

The data element as a double.

Implements [RDBColumn](#).

Definition at line 578 of file `RDBColumnTmpl.cc`.

References `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data`, `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx`, and `RDBColumn::convert()`.

Referenced by `RDB::getData()`, and `RDB::getDataDouble()`.

10.3.3.19 `template<class Tmpl0, class Tmpl1, class Tmpl2> long
RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getDataLong (void) throw (RDBErr) [inline, virtual]`

Returns the value of the current data element, converting if necessary.

Exceptions:

RDBErr error if the user attempts to convert a string column with non-numeric data to a numeric argument.

RDBErr error if the user attempts to convert a string column representing a floating point number to an integer argument.

Returns:

The data element as a long.

Implements [RDBColumn](#).

Definition at line 608 of file RDBColumnTmpl.cc.

References `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data`, `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx`, and `RDBColumn::convert()`.

Referenced by `RDB::getData()`, and `RDB::getDataLong()`.

10.3.3.20 `template<class Tmpl0, class Tmpl1, class Tmpl2> string
RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getDataString (void) throw (RDBErr) [inline, virtual]`

Returns the value of the current data element, converting if necessary.

Returns:

The data element as a string.

Implements [RDBColumn](#).

Definition at line 635 of file RDBColumnTmpl.cc.

References `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data`, `RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx`, and `RDBColumn::convert()`.

Referenced by `RDB::getData()`, and `RDB::getDataString()`.

10.3.3.21 `template<class Tmpl0, class Tmpl1, class Tmpl2> istream &
RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::read (istream & is) throw (RDBErr) [inline, protected, virtual]`

Called by the stream insertion operator.

Parameters:

is input stream.

Returns:

The input stream.

Called by the [RDBColumn](#) stream extraction operator.

Implements [RDBColumn](#).

Definition at line 666 of file RDBColumnTmpl.cc.

References [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data](#), [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx](#), and [RDBColumn::extract\(\)](#).

10.3.3.22 `template<class Tmpl0, class Tmpl1, class Tmpl2> ostream & RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::write (ostream & os) const` [inline, protected, virtual]

Called by the stream extraction operator.

Parameters:

os output stream.

Returns:

The output stream.

Called by the [RDBColumn](#) stream insertion operator.

Implements [RDBColumn](#).

Definition at line 696 of file RDBColumnTmpl.cc.

References [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data](#), [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx](#), and [RDBColumn::insert\(\)](#).

10.3.3.23 `template<class Tmpl0, class Tmpl1, class Tmpl2> void RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::cleanup (void)` [inline, protected]

Deletes resources allocated by [RDBColumnTmpl](#) object.

Frees memory allocated by this object.

Definition at line 710 of file RDBColumnTmpl.cc.

References [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data](#), and [RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_mine](#).

Referenced by RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::mapData(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::operator=(), and RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::~~RDBColumnTmpl().

10.3.4 Member Data Documentation

10.3.4.1 `template<class Tmpl0, class Tmpl1, class Tmpl2> Tmpl0* RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_data` [protected]

Pointer to the data managed by object.

Definition at line 120 of file RDBColumnTmpl.h.

Referenced by RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::cleanup(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getData(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getDataDouble(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getDataLong(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getDataString(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::mapData(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::newGroup(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::operator=(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::RDBColumnTmpl(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::read(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::setData(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::setGroup(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::setGroupValue(), and RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::write().

10.3.4.2 `template<class Tmpl0, class Tmpl1, class Tmpl2> size_t RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::_idx` [protected]

Index into the data.

Definition at line 122 of file RDBColumnTmpl.h.

Referenced by RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::advanceIdx(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getData(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getDataDouble(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getDataLong(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::getDataString(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::mapData(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::newGroup(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::operator=(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::RDBColumnTmpl(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::read(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::rewind(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::setData(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::setGroup(), RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::setGroupValue(), and RDBColumnTmpl< Tmpl0, Tmpl1, Tmpl2 >::write().

10.3.4.3 `template<class Tmplt0, class Tmplt1, class Tmplt2> size_t RDBColumnTmplt< Tmplt0, Tmplt1, Tmplt2 >::_nelems` [protected]

Number of elements of data.

Definition at line 124 of file RDBColumnTmplt.h.

Referenced by `RDBColumnTmplt< Tmplt0, Tmplt1, Tmplt2 >::advanceIdx()`, `RDBColumnTmplt< Tmplt0, Tmplt1, Tmplt2 >::mapData()`, `RDBColumnTmplt< Tmplt0, Tmplt1, Tmplt2 >::newGroup()`, `RDBColumnTmplt< Tmplt0, Tmplt1, Tmplt2 >::operator=()`, `RDBColumnTmplt< Tmplt0, Tmplt1, Tmplt2 >::RDBColumnTmplt()`, `RDBColumnTmplt< Tmplt0, Tmplt1, Tmplt2 >::setGroup()`, and `RDBColumnTmplt< Tmplt0, Tmplt1, Tmplt2 >::setGroupValue()`.

10.3.4.4 `template<class Tmplt0, class Tmplt1, class Tmplt2> bool RDBColumnTmplt< Tmplt0, Tmplt1, Tmplt2 >::_mine` [protected]

Indicates that [RDBColumnTmplt](#) is responsible for deallocating the data.

Definition at line 126 of file RDBColumnTmplt.h.

Referenced by `RDBColumnTmplt< Tmplt0, Tmplt1, Tmplt2 >::cleanup()`, `RDBColumnTmplt< Tmplt0, Tmplt1, Tmplt2 >::mapData()`, `RDBColumnTmplt< Tmplt0, Tmplt1, Tmplt2 >::operator=()`, `RDBColumnTmplt< Tmplt0, Tmplt1, Tmplt2 >::RDBColumnTmplt()`, and `RDBColumnTmplt< Tmplt0, Tmplt1, Tmplt2 >::setGroup()`.

10.3.4.5 `template<class Tmplt0, class Tmplt1, class Tmplt2> Tmplt0 RDBColumnTmplt< Tmplt0, Tmplt1, Tmplt2 >::_groupvalue` [protected]

Current group value.

Definition at line 129 of file RDBColumnTmplt.h.

Referenced by `RDBColumnTmplt< Tmplt0, Tmplt1, Tmplt2 >::newGroup()`, and `RDBColumnTmplt< Tmplt0, Tmplt1, Tmplt2 >::setGroupValue()`.

The documentation for this class was generated from the following files:

- RDBColumnTmplt.h
- RDBColumnTmplt.cc

10.4 RDBComment Class Reference

Provides interface for manipulating [RDB](#) comments.

```
#include <RDBComment.h>
```

Public Member Functions

Constructing, destructing, and initializing RDBComment objects.

- [RDBComment](#) (const string &comment="") throw (RDBErr)
Parses comment string for [RDB](#) comment structure.
- [RDBComment](#) (const [RDBComment](#) &rdbcomment)
Copy [RDBComment](#) object.
- [~RDBComment](#) (void)
Destructor has nothing to do.
- const [RDBComment](#) & [operator=](#) (const [RDBComment](#) &rdbcomment)
Copy [RDBComment](#) object.
- const [RDBComment](#) & [operator=](#) (const string &rdbcomment)
Copy string to [RDBComment](#) object.

Data member initializers.

- void [setComment](#) (const string &comment) throw (RDBErr)
Parses comment string for [RDB](#) comment elements.
- void [setCommentText](#) (const string &comment)
Parses string for [RDB](#) comment elements.
- void [setKeyword](#) (const string &keyword) throw (RDBErr)
Set just the comment keyword.
- void [setValue](#) (const string &value) throw (RDBErr)
Set just the comment value.

Data member accessors.

- string [getComment](#) (void) const
Return the full comment.
- string [getCommentText](#) (void) const
Return the full comment text.
- string [getKeyword](#) (void) const

Return the keyword, if any.

- string [getValue](#) (void) const
Return the keyword's value, if any.

Friends

Stream insertion and extraction operators.

- istream & [operator>>](#) (istream &is, [RDBComment](#) &rdbcomment) throw (RDBErr)
Read comment from input stream.
- ostream & [operator<<](#) (ostream &os, const [RDBComment](#) &rdbcomment)
Write comment to output stream.

10.4.1 Detailed Description

Provides interface for manipulating [RDB](#) comments.

Definition at line 35 of file RDBComment.h.

10.4.2 Constructor & Destructor Documentation

10.4.2.1 RDBComment::RDBComment (const string & *comment* = "") throw (RDBErr)

Parses comment string for [RDB](#) comment structure.

Parameters:

comment the comment string.

Assigns the string comment to the RDBComment's data member. Parses for key-word=value pairs.

Definition at line 102 of file RDBComment.cc.

10.4.2.2 RDBComment::RDBComment (const RDBComment & *rdbcomment*)

Copy [RDBComment](#) object.

Parameters:

rdcomment a reference to the [RDBComment](#) to copy.

Copies the [RDBComment](#) into this object.

Definition at line 125 of file RDBComment.cc.

References operator=().

10.4.2.3 RDBComment::~~RDBComment (void)

Destructor has nothing to do.

Nothing to do.

Definition at line 137 of file RDBComment.cc.

10.4.3 Member Function Documentation**10.4.3.1 const RDBComment & RDBComment::operator= (const RDBComment & *rdcomment*)**

Copy [RDBComment](#) object.

Parameters:

rdcomment a reference to the [RDBComment](#) to copy.

Returns:

A reference to this.

Definition at line 150 of file RDBComment.cc.

References _comment, _keyword, and _value.

Referenced by RDBComment().

10.4.3.2 const RDBComment & RDBComment::operator= (const string & *comment*)

Copy string to [RDBComment](#) object.

Parameters:

comment a string comment to copy.

Returns:

A reference to this.

Definition at line 172 of file RDBComment.cc.

References `setCommentText()`.

10.4.3.3 void RDBComment::setComment (const string & *comment*) throw (RDBErr)

Parses comment string for [RDB](#) comment elements.

Parameters:

comment Strips leading '#' character if present. If next character is ':', then it searches for a keyword=value pair.

Definition at line 190 of file RDBComment.cc.

References `setCommentText()`.

Referenced by `setKeyword()`, and `setValue()`.

10.4.3.4 void RDBComment::setCommentText (const string & *comment*)

Parses string for [RDB](#) comment elements.

Parameters:

comment Strips leading '#' character if present. If next character is ':', then it searches for a keyword=value pair.

Definition at line 222 of file RDBComment.cc.

Referenced by `operator=()`, and `setComment()`.

10.4.3.5 void RDBComment::setKeyword (const string & *keyword*) throw (RDBErr)

Set just the comment keyword.

Parameters:

keyword the keyword part of a keyword=value pair.

Updates just the keyword half of a keyword=value pair.

Definition at line 278 of file RDBComment.cc.

References `setComment()`.

10.4.3.6 void RDBComment::setValue (const string & *value*) throw (RDBErr)

Set just the comment value.

Parameters:

value the value part of a keyword=value pair.

Updates just the value half of a keyword=value pair.

Definition at line 302 of file RDBComment.cc.

References setComment().

10.4.3.7 string RDBComment::getComment (void) const

Return the full comment.

Returns:

The comment string.

Definition at line 324 of file RDBComment.cc.

10.4.3.8 string RDBComment::getCommentText (void) const

Return the full comment text.

Returns:

The comment string.

Definition at line 346 of file RDBComment.cc.

10.4.3.9 string RDBComment::getKeyword (void) const

Return the keyword, if any.

Returns:

The keyword half of a keyword=value pair.

Definition at line 359 of file RDBComment.cc.

10.4.3.10 string RDBComment::getValue (void) const

Return the keyword's value, if any.

Returns:

The value half of a keyword=value pair.

Definition at line 372 of file RDBComment.cc.

10.4.4 Friends And Related Function Documentation

10.4.4.1 istream& operator>> (istream & *is*, RDBComment & *rdbcomment*) throw (RDBErr) [friend]

Read comment from input stream.

Parameters:

is the input stream.

rdbcomment the comment to fill.

Returns:

A reference to the input stream.

If the line is an [RDB](#) comment line, i.e. it starts with a '#', then fill the comment. Otherwise, set ios::failbit.

Definition at line 38 of file RDBComment.cc.

10.4.4.2 ostream& operator<< (ostream & *os*, const RDBComment & *rdbcomment*) [friend]

Write comment to output stream.

Parameters:

os the output stream.

rdbcomment the comment to print.

Returns:

A reference to the output stream

Places the comment on the output stream. Appends a '#' character if its a plain comment or a "#:" string if its a keyword/value comment.

Definition at line 73 of file RDBComment.cc.

The documentation for this class was generated from the following files:

- RDBComment.h
- RDBComment.cc

10.5 RDBErr Class Reference

The parent class for all [RDB](#) related exceptions.

```
#include <RDBErr.h>
```

Public Member Functions

- [RDBErr](#) (const string &msg)
Constructor.
- [RDBErr](#) ()
Constructor.
- [~RDBErr](#) () throw ()
Destructor.

10.5.1 Detailed Description

The parent class for all [RDB](#) related exceptions.

Definition at line 33 of file RDBErr.h.

10.5.2 Constructor & Destructor Documentation

10.5.2.1 RDBErr::RDBErr (const string & msg)

Constructor.

Definition at line 27 of file RDBErr.cc.

10.5.2.2 RDBErr::RDBErr ()

Constructor.

Definition at line 29 of file RDBErr.cc.

10.5.2.3 RDBErr::~~RDBErr () throw ()

Destructor.

Definition at line 31 of file RDBErr.cc.


The documentation for this class was generated from the following files:

- RDBErr.h
- RDBErr.cc


10.6 simpleRDBTable< Type > Class Template Reference

```
#include <simpleRDBTable.h>
```

Inheritance diagram for simpleRDBTable< Type >:



Collaboration diagram for simpleRDBTable< Type >:



Public Member Functions

- **simpleRDBTable** (const string &fname, const int mode, const char *header[]) throw (Exception)
- void **print** (ostream &os) const
- Type * **readRow** () throw (Exception)
*Read a row of the **RDB** table.*

Static Public Member Functions

- static void **getData** (RDBColumn *rdbcol, string &val) throw (Exception)
*Given an **RDBColumn**, get a string value.*
- static void **getData** (RDBColumn *rdbcol, int &val) throw (Exception)
*Given an **RDBColumn**, get an integer value.*
- static void **getData** (RDBColumn *rdbcol, long &val) throw (Exception)
*Given an **RDBColumn**, get a long value.*
- static void **getData** (RDBColumn *rdbcol, double &val) throw (Exception)
*Given an **RDBColumn**, get a double value.*

Protected Attributes

- const char ** **rdb_header**
- RDBColumn ** **rdb_column**

Friends

- ostream & **operator**<< (ostream &os, simpleRDBTable< Type > &a)
- ostream & **operator**<< (ostream &os, simpleRDBTable< Type > *a)

10.6.1 Detailed Description

template<class Type> class simpleRDBTable< Type >

A simple interface to the RDB++ read a row of an rdb table to initialize a class Type. The class Type must have a constructor with the following prototype:

Type(const char* header[], RDBColumn** rdb_column) throw(Exception)

Definition at line 48 of file simpleRDBTable.h.

10.6.2 Member Function Documentation

10.6.2.1 `template<class Type> void simpleRDBTable< Type >::getData (RDB-Column * rdbcol, string & val) throw (Exception) [inline, static]`

Given an [RDBColumn](#), get a string value.

Definition at line 86 of file simpleRDBTable.cc.

10.6.2.2 `template<class Type> void simpleRDBTable< Type >::getData (RDB-Column * rdbcol, int & val) throw (Exception) [inline, static]`

Given an [RDBColumn](#), get an integer value.

Definition at line 98 of file simpleRDBTable.cc.

10.6.2.3 `template<class Type> void simpleRDBTable< Type >::getData (RDB-Column * rdbcol, long & val) throw (Exception) [inline, static]`

Given an [RDBColumn](#), get a long value.

Definition at line 122 of file simpleRDBTable.cc.

10.6.2.4 `template<class Type> void simpleRDBTable< Type >::getData (RDB-Column * rdbcol, double & val) throw (Exception) [inline, static]`

Given an [RDBColumn](#), get a double value.

Definition at line 145 of file simpleRDBTable.cc.

10.6.2.5 `template<class Type> Type * simpleRDBTable< Type >::readRow () throw (Exception) [inline]`

Read a row of the [RDB](#) table.

Definition at line 191 of file simpleRDBTable.cc.

References [RDB::_isptr](#), and [RDB::read\(\)](#).

The documentation for this class was generated from the following files:

- [simpleRDBTable.h](#)
- [simpleRDBTable.cc](#)

Index

- ~RDB
 - RDB, [27](#)
- ~RDBColumn
 - RDBColumn, [78](#)
- ~RDBColumnTmpl
 - RDBColumnTmpl, [101](#)
- ~RDBComment
 - RDBComment, [116](#)
- ~RDBErr
 - RDBErr, [120](#)
- _autoidx
 - RDB, [68](#)
- _changed
 - RDBColumn, [96](#)
- _cols
 - RDB, [69](#)
- _comms
 - RDB, [69](#)
- _data
 - RDBColumnTmpl, [112](#)
- _def
 - RDBColumn, [95](#)
- _desc
 - RDBColumn, [96](#)
- _errno
 - RDBColumn, [96](#)
- _filename
 - RDB, [66](#)
- _firstread
 - RDB, [68](#)
- _frownum
 - RDB, [68](#)
- _group
 - RDBColumn, [97](#)
- _groupvalue
 - RDBColumnTmpl, [113](#)
- _idx
 - RDBColumnTmpl, [112](#)
- _initgroup
 - RDBColumn, [97](#)
- _isptr
 - RDB, [66](#)
- _just
 - RDBColumn, [95](#)
- _knowrows
 - RDB, [68](#)
- _lastread
 - RDB, [69](#)
- _line
 - RDB, [70](#)
- _mine
 - RDBColumnTmpl, [113](#)
- _mode
 - RDB, [66](#)
- _mycols
 - RDB, [69](#)
- _myisptr
 - RDB, [67](#)
- _myosptr
 - RDB, [67](#)
- _name
 - RDBColumn, [95](#)
- _ncols
 - RDB, [67](#)
- _ncomms
 - RDB, [67](#)
- _nelems
 - RDBColumnTmpl, [112](#)
- _nrcol
 - RDB, [69](#)
- _nrows
 - RDB, [68](#)
- _osptr
 - RDB, [67](#)
- _precision
 - RDBColumn, [96](#)
- _rewindto
 - RDB, [67](#)
- _rownum
 - RDB, [68](#)
- _strstrm
 - RDBColumn, [96](#)
- _throw
 - RDBColumn, [96](#)

- `_type`
 - RDBColumn, 95
 - `_width`
 - RDBColumn, 95
 - `_writehdr`
 - RDB, 69
- `advanceIdx`
 - RDB, 32
 - RDBColumn, 79
 - RDBColumnTplt, 103
- `autoIdx`
 - RDB, 31
- `cleanup`
 - RDBColumnTplt, 111
- `close`
 - RDB, 29
- `convert`
 - RDBColumn, 87–90
- `Err`
 - RDBColumn, 77
- `extract`
 - RDBColumn, 91
- `getColumn`
 - RDB, 38
- `getComment`
 - RDB, 35, 36
 - RDBComment, 118
- `getCommentText`
 - RDBComment, 118
- `getData`
 - RDB, 46, 47, 58, 59
 - RDBColumn, 86
 - RDBColumnTplt, 107, 108
 - simpleRDBTable, 123
- `getDataDouble`
 - RDB, 50, 62
 - RDBColumn, 87
 - RDBColumnTplt, 109
- `getDataLong`
 - RDB, 50, 63
 - RDBColumn, 87
 - RDBColumnTplt, 109
- `getDataString`
 - RDB, 51, 63
 - RDBColumn, 87
 - RDBColumnTplt, 110
- `getDef`
 - RDB, 44, 48, 56, 60
 - RDBColumn, 84
- `getDesc`
 - RDB, 46, 49, 58, 62
 - RDBColumn, 85
- `getErr`
 - RDBColumn, 86
- `getErrNo`
 - RDBColumn, 86
- `getGroup`
 - RDB, 33
 - RDBColumn, 80
- `getJust`
 - RDB, 45, 49, 58, 61
 - RDBColumn, 85
- `getKeyword`
 - RDBComment, 118
- `getName`
 - RDB, 44, 47, 56, 60
 - RDBColumn, 84
- `getPrecision`
 - RDBColumn, 85
- `getThrow`
 - RDBColumn, 86
- `getType`
 - RDB, 45, 49, 57, 61
 - RDBColumn, 85
- `getValue`
 - RDBComment, 118
- `getWidth`
 - RDB, 45, 48, 57, 60
 - RDBColumn, 85
- `insert`
 - RDBColumn, 92, 93
- `Just`
 - RDBColumn, 77
- `mapData`
 - RDB, 41, 42, 54

- RDBColumn, 84
- RDBColumnTplt, 107
- nColumns
 - RDB, 64
- nComments
 - RDB, 63
- newGroup
 - RDB, 33
 - RDBColumn, 80
 - RDBColumnTplt, 105
- nRows
 - RDB, 64
- open
 - RDB, 27–29
- operator<<
 - RDB, 66
 - RDBColumn, 94
 - RDBComment, 119
- operator>>
 - RDB, 65
 - RDBColumn, 93, 94
 - RDBComment, 119
- operator=
 - RDBColumn, 78, 79
 - RDBColumnTplt, 102, 103
 - RDBComment, 116
- parseHeader
 - RDB, 64
- parseLine
 - RDB, 65
- RDB, 15
 - ~RDB, 27
 - _autoidx, 68
 - _cols, 69
 - _comms, 69
 - _filename, 66
 - _firstread, 68
 - _frownum, 68
 - _isptr, 66
 - _knowrows, 68
 - _lastread, 69
 - _line, 70
 - _mode, 66
 - _mycols, 69
 - _myisptr, 67
 - _myosptr, 67
 - _ncols, 67
 - _ncomms, 67
 - _nrcol, 69
 - _nrows, 68
 - _osptr, 67
 - _rewindto, 67
 - _rownum, 68
 - _writehdr, 69
 - advanceIdx, 32
 - autoIdx, 31
 - close, 29
 - getColumn, 38
 - getComment, 35, 36
 - getData, 46, 47, 58, 59
 - getDataDouble, 50, 62
 - getDataLong, 50, 63
 - getDataString, 51, 63
 - getDef, 44, 48, 56, 60
 - getDesc, 46, 49, 58, 62
 - getGroup, 33
 - getJust, 45, 49, 58, 61
 - getName, 44, 47, 56, 60
 - getType, 45, 49, 57, 61
 - getWidth, 45, 48, 57, 60
 - mapData, 41, 42, 54
 - nColumns, 64
 - nComments, 63
 - newGroup, 33
 - nRows, 64
 - open, 27–29
 - operator<<, 66
 - operator>>, 65
 - parseHeader, 64
 - parseLine, 65
 - RDB, 26, 27
 - read, 29
 - rewind, 30
 - setColumn, 36–38
 - setComment, 34, 35
 - setData, 43, 55, 56
 - setDef, 39, 52
 - setDesc, 41, 53

- setGroup, 32
- setJust, 40, 53
- setName, 39, 51
- setType, 40, 52
- setWidth, 40, 52
- Status, 26
- write, 30
- RDBColumn, 70
 - ~RDBColumn, 78
 - _changed, 96
 - _def, 95
 - _desc, 96
 - _errno, 96
 - _group, 97
 - _initgroup, 97
 - _just, 95
 - _name, 95
 - _precision, 96
 - _strstm, 96
 - _throw, 96
 - _type, 95
 - _width, 95
- advanceIdx, 79
- convert, 87–90
- Err, 77
- extract, 91
- getData, 86
- getDataDouble, 87
- getDataLong, 87
- getDataString, 87
- getDef, 84
- getDesc, 85
- getErr, 86
- getErrNo, 86
- getGroup, 80
- getJust, 85
- getName, 84
- getPrecision, 85
- getThrow, 86
- getType, 85
- getWidth, 85
- insert, 92, 93
- Just, 77
- mapData, 84
- newGroup, 80
- operator<<, 94
- operator>>, 93, 94
- operator=, 78, 79
- RDBColumn, 77, 78
- read, 90
- rewind, 79
- setData, 83
- setDef, 81
- setDesc, 82
- setErrNo, 83
- setGroup, 79
- setGroupValue, 80
- setJust, 82
- setName, 80
- setPrecision, 82
- setThrow, 83
- setType, 81
- setWidth, 81
- Status, 77
- Type, 77
- write, 92
- RDBColumnTplt, 97
 - ~RDBColumnTplt, 101
 - _data, 112
 - _groupvalue, 113
 - _idx, 112
 - _mine, 113
 - _nelems, 112
 - advanceIdx, 103
 - cleanup, 111
 - getData, 107, 108
 - getDataDouble, 109
 - getDataLong, 109
 - getDataString, 110
 - mapData, 107
 - newGroup, 105
 - operator=, 102, 103
 - RDBColumnTplt, 101
 - read, 110
 - rewind, 104
 - setData, 105, 106
 - setGroup, 104
 - setGroupValue, 104
 - write, 111
- RDBComment, 113
 - ~RDBComment, 116
 - getComment, 118

- getCommentText, [118](#)
- getKeyword, [118](#)
- getValue, [118](#)
- operator<<, [119](#)
- operator>>, [119](#)
- operator=, [116](#)
- RDBComment, [115](#)
- setComment, [117](#)
- setCommentText, [117](#)
- setKeyword, [117](#)
- setValue, [117](#)
- RDBErr, [120](#)
 - ~RDBErr, [120](#)
 - RDBErr, [120](#)
- rdbox/ Directory Reference, [15](#)
- read
 - RDB, [29](#)
 - RDBColumn, [90](#)
 - RDBColumnTplt, [110](#)
- readRow
 - simpleRDBTable, [123](#)
- rewind
 - RDB, [30](#)
 - RDBColumn, [79](#)
 - RDBColumnTplt, [104](#)
- setColumn
 - RDB, [36–38](#)
- setComment
 - RDB, [34, 35](#)
 - RDBComment, [117](#)
- setCommentText
 - RDBComment, [117](#)
- setData
 - RDB, [43, 55, 56](#)
 - RDBColumn, [83](#)
 - RDBColumnTplt, [105, 106](#)
- setDef
 - RDB, [39, 52](#)
 - RDBColumn, [81](#)
- setDesc
 - RDB, [41, 53](#)
 - RDBColumn, [82](#)
- setErrNo
 - RDBColumn, [83](#)
- setGroup
 - RDB, [32](#)
 - RDBColumn, [79](#)
 - RDBColumnTplt, [104](#)
- setGroupValue
 - RDBColumn, [80](#)
 - RDBColumnTplt, [104](#)
- setJust
 - RDB, [40, 53](#)
 - RDBColumn, [82](#)
- setKeyword
 - RDBComment, [117](#)
- setName
 - RDB, [39, 51](#)
 - RDBColumn, [80](#)
- setPrecision
 - RDBColumn, [82](#)
- setThrow
 - RDBColumn, [83](#)
- setType
 - RDB, [40, 52](#)
 - RDBColumn, [81](#)
- setValue
 - RDBComment, [117](#)
- setWidth
 - RDB, [40, 52](#)
 - RDBColumn, [81](#)
- simpleRDBTable, [121](#)
 - getData, [123](#)
 - readRow, [123](#)
- Status
 - RDB, [26](#)
 - RDBColumn, [77](#)
- Type
 - RDBColumn, [77](#)
- write
 - RDB, [30](#)
 - RDBColumn, [92](#)
 - RDBColumnTplt, [111](#)