
NAME

scatfile_convert - converts binary format scattering distributions to FITS format

SYNOPSIS

scatfile_convert [OPTIONS]

DESCRIPTION

For each line the *scatter_db*, **scatfile_convert** converts the binary format scattering distribution to a FITS file. Each scattering distribution file is placed in a single FITS binary table.

The *hdosxform_db* and *mirror_db* are used to determine the zone geometry in the body center coordinates.

OPTIONS

The following options are supported:

hdosxformdb

RDB database mirror dimensions. See *FILES*.

mirrordb

RDB database of mirror positions. See *FILES*.

scatterdb

RDB database of zone positions and scattering distribution files. See *FILES*.

outputdir

Directory into which the output files are written. The output files will be named after the binary *scat_files* in the *scatter_db*.

help

Print brief usage information and exit.

usage

Print usage information and exit.

version

Print version information and exit.

EXAMPLE

```
scatfile_convert \
--hdosxformdb /proj/axaf/simul/databases/mirror/hdos_xform.rdb \
--mirrordb /proj/axaf/simul/databases/mirror/EKCHDOS06.rdb \
--scatterdb /proj/axaf/simul/databases/scatter/HDOS_980623a.rdb \
--outputdir ./HDOS/980623a/tables
```

FILES**HDOS Transform Database**

The HDOS transform database must contain the mirror name, mirror end cut position, and mirror length in the *mirror*, *Z_ec*, and *L* columns respectively.

Mirror Database

The mirror database must contain the mirror name and Z position of the body center of the optic in the *mirror* and *z0* columns respectively.

Scatter Database

The scatter database must contain the mirror name, Z position of the zone minimum, Z position of the zone maximum, and the binary format scattering distribution file in the *mirror*, *zmin*, *zmax*, and *scat_file* columns respectively.

Scattering Distribution Files

These files are assumed to be binary format files with the following structure:

integer

an integer representing the number of elements in the scattering distribution(ndist).

float

a float representing energy times sine of the graze angle(esa).

float

a float representing the minimum probability in the scattering distribution(p0).

float

a float representing the distance between probabilities in the scattering distribution(pdelta).

float

a float representing the maximum probability in the scattering distribution(ptop).

float

a float representing the normalization factor for the value being raise to a power(normtop).

float

a float representing the power to which the normalized(normtop) value is raised(powtop).

float

a number(ndist) of floats representing the scattering distribution (pdist).

COPYRIGHT & LICENSE

Copyright 2006 Smithsonian Astrophysical Observatory

This software is released under the GNU General Public License. You may find a copy at <http://www.fsf.org/copyleft/gpl.html>

VERSION

This documents version @VERSION@ of **scatfile_convert**.

AUTHOR

M. Tibbetts (mtibbetts@cfa.harvard.edu)