



Bugs: dmgroup

Bugs

1. *Minimum and maximum values for the `binspec` parameter*

If there is no min/max given in the `binspec` parameter, the tool returns the min/max for the datatype for the specified column. If this is a large range, it will fail with

```
# dmgroup (CIAO 3.4): dsALLOCERR -- ERROR: Could not allocate memory.
```

Workarounds:

1. Provide a binning specification in the `binspec` parameter.
2. If the column range is missing or too large, one may be forced by filtering the column. For example, to establish a PHA range:

```
unix% pset dmgroup infile="acis_evt2.fits[pha=1:4096]"
```

The Chandra X-Ray Center (CXC) is operated for NASA by the Smithsonian Astrophysical Observatory.
60 Garden Street, Cambridge, MA 02138 USA.
Smithsonian Institution, Copyright © 1998–2006. All rights reserved.

URL:
<http://cxc.harvard.edu/ciao3.4/bugs/dmgroup.html>
Last modified: 21 November 2006

Bugs: dmgroup – CIAO 3.4