



---

## I/O Bugs: notice

### Bugs

1. *If the instrument background set and you try to filter on energy, you will get a warning.*

However, if you then add "source" to the filtering syntax to correct the command, an error is printed and the filter command is ignored:

```
sherpa> ignore all
sherpa> notice energy :0.3,7:
WARNING: filter command ignored -- cannot be applied to dataset 1
WARNING: filter command ignored -- cannot be applied to dataset 1
sherpa> notice source energy :0.3,7:
Error: filter stack cannot be reduced; filter reset.

sherpa> notice source energy :0.3,7:
sherpa>
```

As shown, issuing the correct filter a second time works properly.

